

# Natural System Error Messages 7501-7550

## **NAT7508: Compression table full.**

Text	Compression table full.
Actn.	Increase value of CMPRTSZ parameter in Natural parameter module.

## **NAT7509: GETMAIN failed for Entire.**

Text	GETMAIN failed for Entire.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

## **NAT7510: GETMAIN failed for CON-NECT.**

Text	GETMAIN failed for CON-NECT.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

## **NAT7511: GETMAIN failed for TRS.**

Text	GETMAIN failed for TRS.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

## **NAT7512: GETMAIN failed for VSAM.**

Text	GETMAIN failed for VSAM.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

## **NAT7513: GETMAIN failed for EDITOR.**

Text	GETMAIN failed for EDITOR.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

**NAT7514: GETMAIN failed for PROCESS (ASIZE).**

Text	GETMAIN failed for PROCESS (ASIZE).
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment: Increase your region size or increase the size of your Natural thread when running in a thread environment.

**NAT7515: GETMAIN failed for DEBUG.**

Text	GETMAIN failed for DEBUG.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

**NAT7516: GETMAIN failed for PC-CONNECTION.**

Text	GETMAIN failed for PC-CONNECTION.
Expl.	The subsystem using the corresponding buffer will not be able to run.
Actn.	Restart Natural in a larger environment.

**NAT7540: GETMAIN failed for DB2.**

Text	GETMAIN failed for DB2.
------	-------------------------

**NAT7543: GETMAIN failed for USERBUF buffer.**

Text	GETMAIN failed for USERBUF buffer.
------	------------------------------------

**NAT7544: GETMAIN request failed for :1:.**

Text	GETMAIN request failed for ....
Expl.	The requested buffer size exceeded the available space in the current thread/partition/region/task.
Actn.	Either decrease the size of the buffer, or start Natural in a larger thread/partition/region/task.

**NAT7545: GETMAIN of :1: for :2: buffer failed (:3:/:4:).**

Text	GETMAIN of ... for ... buffer failed (reason/response).
Expl.	The requested buffer size exceeds the available space in the current thread/partition/region/task. Possible reason/response codes: (04/0) Upper thread limit exceeded. (52/n) Non-zero response code n from operating (sub-)system GETMAIN. (56/0) Thread overflow size OVSIZE exceeded. For any other reason code, please refer to the Natural messages and codes documentation.
Actn.	Either decrease the size of the buffer, or start Natural in a larger thread/partition/region/task, or if (56/0) increase OVSIZE.

**NAT7546: FREEMAIN for :1: buffer failed (:2:/:3:).**

Text	FREEMAIN for ... buffer failed (reason/response).
Expl.	An internal error has occurred. For an explanation of the reason/response code, see the Natural messages and codes documentation.
Actn.	Please contact Software AG support.

**NAT7548: :1: unavailable, reason/reason code :2:/:3:.**

Text	... unavailable, reason/reason code .../....
Expl.	The indicated Natural component is not available. Possible reasons are that a subcomponent or a module required to execute the component is not available or not accessible. Possible reason codes are: 04 - Initialization failed. 08 - GETMAIN failed. 12 - Module could not be loaded. 16 - Module has not been linked to Natural. 20 - Subcomponent does not run with this Natural version
Actn.	Contact your Natural administrator.