

Starting and Terminating the Configuration Utility

This document covers the following topics:

- Starting the Configuration Utility
 - Terminating the Configuration Utility
 - Performing a Function while Starting the Configuration Utility
-

Starting the Configuration Utility

The way you start the Configuration Utility depends on how the system has been configured at your site. For most installations, you start it as described below.

▶ To start the Configuration Utility

- Enter the following command at the OpenVMS DCL prompt:

```
natnparm
```

where *nn* is the current version number.

The **Natural Configuration Utility** screen appears.

```
09/05/2007                Natural Configuration Utility                User: (Config)
                               V 6.3.4                               File: NATPARM

+-----+-----+-----+-----+
|File           Edit           Configuration           Search           |
+-----+-----+-----+-----+

Natural Parameter File Administration
```

Note:

The **Configuration** menu is only shown in the **Natural Configuration Utility** screen if you have been defined as configuration administrator in the local configuration file.

The name of the parameter file which is currently active is shown in the top right-hand corner of the screen.

When "(Admin)" or "(Config)" is shown in the top right-hand corner of the screen (instead of a user ID), you have been defined as an administrator in the local configuration file.

For further information, see *Administrator Assignments* in the local configuration file.

Terminating the Configuration Utility

When you terminate the Configuration Utility and you have not yet saved your changes, a window appears asking whether you want to save now.

To terminate the Configuration Utility

- From the **File** menu, choose **Exit**.

Performing a Function while Starting the Configuration Utility

You can perform several functions automatically when starting the Configuration Utility.

The following functions can be specified after the `natnnparm` command at the OpenVMS DCL prompt.

Function	Description
<code>exit</code>	Terminates the Configuration Utility.
<code>import=parameter-file</code>	Imports the specified parameter file.
<code>export=parameter-file</code>	Exports the specified parameter file.
<code>parm=parameter-file</code>	Opens the specified parameter file.
<code>save</code>	Saves a parameter file.
<code>save=new-parameter-file-name</code>	Saves a parameter file under a different name.

Multiple functions can be specified one after the other (see the examples below).

Examples

- Invoke the Configuration Utility and open the specified parameter file so that it can be edited immediately:

```
natnnparm parm=parameter-file
```

- Invoke the Configuration Utility, open the specified parameter file, and save it as a new file with the specified name:

```
natnnparm parm=parameter-file save=new-parameter-file-name
```

- Invoke the Configuration Utility, export the specified parameter file and terminate the Configuration Utility:

```
natnnparm export=parameter-file exit
```

- Invoke the Configuration Utility, import the specified parameter file and save it under the name of the imported file:

```
natnnparm import=parameter-file save
```