# **Column Specification Control**

This chapter covers the following topics:

- Description
- Attributes for Column Specification Control
- COLUMN-TYPEs and their Attributes
- Events

#### **Description**

A column specification control is a dialog element that defines the columns in a table control. (A table control is a dialog element that represents a spreadsheet.) Once the table control defines the spreadsheet as such, its columns are defined by adding column-specification controls.

### **Attributes for Column Specification Control**

| Attribute Name             | Query | Set/Modify | In Attr. Window |
|----------------------------|-------|------------|-----------------|
| CLIENT-DATA                | X     | X/X        |                 |
| CLIENT-HANDLE              | X     | X/X        |                 |
| CLIENT-KEY                 | X     | X/X        |                 |
| CLIENT-VALUE               | X     | X/X        |                 |
| COLUMN-TYPE                | X     | X/-        | X               |
| DIL-TEXT                   | X     | X/X        | X               |
| FIRST-CHILD                | X     | -/-        |                 |
| HELP-ID                    | X     | X/X        | X               |
| LAST-CHILD                 | X     | -/-        |                 |
| LENGTH                     | X     | X/-        | X               |
| MODIFIABLE (input-field)   | X     | X/X        | X               |
| MODIFIABLE (selection-box) | X     | X/-        | X               |
| PARENT                     | X     | X/-        |                 |
| PREDECESSOR                | X     | -/-        |                 |
| RECTANGLE-W                | X     | X/X        | X               |
| STRING                     | X     | X/X        | X               |
| STYLE                      | X     | X/-        |                 |
| SUCCESSOR                  | X     | X/-        |                 |
| SUPPRESS-CHANGE-EVENT      | X     | -/-        |                 |
| SUPPRESS-CLICK-EVENT       | X     | X/X        |                 |
| SUPPRESS-DBL-CLICK-EVENT   | X     | X/X        |                 |
| SUPPRESS-ENTER-EVENT       | X     | X/X        |                 |
| SUPPRESS-ENTER-CELL-EVENT  | X     | X/X        |                 |
| SUPPRESS-FILL-EVENT        | X     | X/X        |                 |
| SUPPRESS-LEAVE-EVENT       | X     | X/X        |                 |
| SUPPRESS-LEAVE-CELL-EVENT  | X     | X/X        |                 |
| ТҮРЕ                       | X     | X/-        |                 |
| VISIBLE                    | X     | -/-        |                 |

#### **COLUMN-TYPEs and their Attributes**

The attributes that are valid for column specification controls in general are not always available depending on the value of the attribute COLUMN-TYPE. Such a value might be, for example, "toggle button control". The column then consists of cells that can be used like toggle button controls. For these toggle-button cells, only a subset of the attributes is available.

The following table specifies which attributes are *not* applicable to a COLUMN-TYPE.

| COLUMN-TYPE           | Attributes NOT Available  |
|-----------------------|---|
| Input field control   | (All available.)  |
| Selection box control | (All available.)  |
| Selection box item    | DIL-TEXT, HELP-ID, LENGTH, MODIFIABLE, STYLE, SUPPRESS-CHANGE-EVENT, SUPPRESS-CLICK-EVENT, SUPPRESS-DBL-CLICK-EVENT, SUPPRESS-ENTER-EVENT, SUPPRESS-ENTER-CELL-EVENT, SUPPRESS-LEAVE-EVENT, SUPPRESS-LEAVE-CELL-EVENT, VISIBLE. |
| Toggle button control | LENGTH, STYLE, MODIFIABLE.  |

## **Events**

This dialog element does not create events.