

# Push Button Control Attributes Window

## ▶ Accessible Using

1. Double-click on the push-button control; or
  2. if selected: "Control > Attributes" or by selecting 'Attributes...' from the control's context menu or
  3. if selected: ENTER.
- 

## Entries

### Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attributes Window	Represents
<b>Name</b>	Handle name of the push-button control (may be overwritten with another name).
<b>Array...</b>	Dialog box for defining an array of push-button controls.
<b>String</b>	STRING attribute value.
<b>...</b>	Dialog box for determining sources of STRING attribute values.
<b>Font</b>	Output field where the font currently selected is displayed.
<b>...</b>	Dialog box for selecting fonts.
<b>DIL text</b>	DIL-TEXT attribute value (string).
<b>...</b>	Dialog box for determining sources of DIL-TEXT attribute values.
<b>Accelerator</b>	ACCELERATOR attribute value.
<b>...</b>	Dialog box for determining sources of ACCELERATOR attribute values.
<b>Context Menu</b>	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
<b>State:</b>	
<b>Visible</b>	VISIBLE attribute value.
<b>Enabled</b>	ENABLED attribute value.
<b>Help ID</b>	HELP-ID attribute value. You must use the help topic's .h file to map the numerical ID that you enter here to the corresponding help topic ID (created by a markup in the .hlp file).
<b>Style:</b>	
<b>OK Button</b>	STYLE attribute value: if the end user presses ENTER, this button is pushed.
<b>Cancel Button</b>	STYLE attribute value: if the end user presses ESC, this button is pushed.

<b>Entry in Attributes Window</b>	<b>Represents</b>
<b>Command ID</b>	CLIENT-KEY attribute value (used in this context for associating a command ID).
<b>Rectangle:</b>	The following four attributes decide the push button control's x and y axis position, its height and its width on the screen.  <b>X</b> - RECTANGLE-X attribute value. <b>Y</b> - RECTANGLE-Y attribute value. <b>W</b> - RECTANGLE-W attribute value. <b>H</b> - RECTANGLE-H attribute value.
<b>OK</b>	Save settings and exit the window.
<b>Cancel</b>	Exit the window without saving the settings.
<b>Help</b>	Provides online help on the attributes window.