

Scrollbar Control Attributes Window

▶ Accessible Using

1. Double-click on the scroll-bar control; or
 2. if selected: "Control > Attributes" or by selecting 'Attributes...' from the control's context menu or
 3. if selected: ENTER
-

Entries

Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attributes Window	Represents
Name	Handle name of the scroll-bar control (may be overwritten with another name starting with the # sign).
Array...	Dialog box for defining an array of scroll-bar controls.
DIL text	DIL-TEXT attribute value (string).
...	Dialog box for determining sources of DIL-TEXT attribute values.
Help ID	HELP-ID attribute value. You must use the help topic's .h file to map the numerical ID that you enter here to the corresponding help topic ID (created by a markup in the .hlp file).
Context Menu	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
State:	
Visible	VISIBLE attribute value.
Enabled	ENABLED attribute value.
Values:	
Minimum	MIN attribute value (minimum numerical value on the scale).
Maximum	MAX attribute value (maximum numerical value on the scale).
Line	LINE attribute value (number of logical units by which the slider moves if the end user presses the up and down arrow buttons).
Page	PAGE attribute value (number of logical units by which the slider moves if the end user clicks on the scroll-bar control's shaft).
Slider	SLIDER attribute value (position of the slider in between the MIN and MAX values).

Entry in Attributes Window	Represents
Rectangle:	<p>The following four attributes decide the scroll-bar control's x and y axis position, its height and its width on the screen.</p> <p>X - RECTANGLE-X attribute value. Y - RECTANGLE-Y attribute value. W - RECTANGLE-W attribute value. H - RECTANGLE-H attribute value.</p>
Horizontal / Vertical	<p>Mutually exclusive STYLE attribute values: slider will scroll horizontally or vertically.</p> <p>Note: When you edit the STYLE attribute value in the scroll-bar control attributes window, setting "h" instead of "v" and vice versa, the RECTANGLE-H and RECTANGLE-W attribute values are exchanged. The dialog editor thus ensures that the scroll-bar control will not provide for vertical scrolling in a horizontal shape and vice versa.</p>
Foreground color:	
Selection box	FOREGROUND-COLOUR-NAME attribute value.
...	Dialog box for editing FOREGROUND-COLOUR-VALUE attribute value.
Background color:	
Selection box	BACKGROUND-COLOUR-NAME attribute value.
...	Dialog box for editing BACKGROUND-COLOUR-VALUE attribute value.
OK	Save settings and exit the window.
Cancel	Exit the window without saving the settings.
Help	Provides online help on the attributes window.