

# Table Attributes Subwindow

## ▶ Accessible Using

- Select the "Attributes..." button in the table attributes window.
- 

## Entries

### Note:

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

Entry in Attrib. Subwindow	Represents
<b>Name</b>	Handle name of the table (may be overwritten with another name).
<b>Font</b>	Output field where the font currently selected is displayed.
...	Dialog box for selecting fonts.
<b>Header font</b>	Output field where the font currently selected for the table header is displayed.
...	Dialog box for selecting fonts.
<b>DIL text</b>	DIL-TEXT attribute value (string).
...	Dialog box for determining sources of DIL-TEXT attribute values.
<b>Context Menu</b>	CONTEXT-MENU attribute value. Specifies the context menu (if any) associated with the control.
<b>Rectangle:</b>	The following four attributes decide the table's x and y axis position, its height and its width on the screen.  <b>X</b> - RECTANGLE-X attribute value. <b>Y</b> - RECTANGLE-Y attribute value. <b>W</b> - RECTANGLE-W attribute value. <b>H</b> - RECTANGLE-H attribute value.
<b>Row count</b>	ROW-COUNT attribute value.
<b>Row height</b>	ROW-HEIGHT attribute value.
<b>Header height</b>	HEADER-HEIGHT attribute value.
<b>Width 1st col.</b>	FIRST-COLUMN-WIDTH attribute value.
<b>Frozen cols.</b>	FIRST-COLUMN-WIDTH attribute value.
<b>Help ID</b>	HELP-ID attribute value. You must use the help topic's .h file to map the numerical ID that you enter here to the corresponding help topic ID (created by a markup in the .hlp file).
<b>First visible col.</b>	FIRST-VISIBLE-COLUMN attribute value.
<b>First visible row</b>	FIRST-VISIBLE-ROW attribute value.

<b>Entry in Attrib. Subwindow</b>	<b>Represents</b>
<b>Columns header</b>	STYLE attribute value: buttons with field names are displayed at the top of each column.
<b>Extendable</b>	STYLE attribute value: end users can delete and insert rows using DEL and INS.
<b>No lines</b>	STYLE attribute value: the table control is displayed without the lines that normally separate the cells.
<b>Resize columns</b>	STYLE attribute value: end users may resize the columns horizontally.
<b>Single cell selection</b>	STYLE attribute value: if set, end users may only select single cells. If not set, end users may select ranges of cells.
<b>Resize rows</b>	STYLE attribute value: end users may resize the rows vertically.
<b>Whole row selection</b>	STYLE attribute value: selecting an individual cell sets the selection to the entire row.
<b>Draggable columns</b>	STYLE attribute value: if set, end users may drag the columns.
<b>Integral height</b>	STYLE attribute value: partial rows are not displayed.
<b>Foreground color:</b>	
<b>Selection box</b>	FOREGROUND-COLOUR-NAME attribute value.
<b>...</b>	Dialog box for editing FOREGROUND-COLOUR-VALUE attribute value.
<b>Background color:</b>	
<b>Selection box</b>	BACKGROUND-COLOUR-NAME attribute value.
<b>...</b>	Dialog box for editing BACKGROUND-COLOUR-VALUE attribute value.
<b>State:</b>	
<b>Visible</b>	VISIBLE attribute value.
<b>Enabled</b>	ENABLED attribute value.
<b>Modifiable</b>	MODIFIABLE attribute value.
<b>RTL</b>	RTL attribute value. If this entry is checked, the dialog element direction is right-to-left.
<b>Has first column</b>	HAS-FIRST-COLUMN attribute value.
<b>Horizontal scroll bar</b>	HORIZ-SCROLLABLE attribute value.
<b>Vertical scroll bar</b>	VERT-SCROLLABLE attribute value.
<b>OK</b>	Save settings and exit the window.
<b>Cancel</b>	Exit the window without saving the settings.
<b>Help</b>	Provides online help on the attributes window.