

# Text Constant Control Attributes Window

## Accessible Using

1. Double-click on the text constant control; or
  2. if selected: "Control > Attributes" or by selecting 'Attributes...' from the control's context menu or
  3. if selected: ENTER.
- 

## Entries

### **Note:**

For context-sensitive help on attribute entries, select the entry so it has the focus, and press F1.

<b>Entry in Attributes Window</b>	<b>Represents</b>
<b>Name</b>	Handle name of the text constant control (may be overwritten with another name).
<b>Array...</b>	Dialog box for defining an array of text constant controls.
<b>String</b>	STRING attribute value.
<b>...</b>	Dialog box for determining sources of STRING attribute values.
<b>Font</b>	Output field where the font currently selected is displayed.
<b>...</b>	Dialog box for selecting fonts.
<b>Style:</b>	
<b>Left / Centered / Right</b>	Mutually exclusive STYLE attribute values: align output to the left, the center, the right.
<b>Framed</b>	STYLE attribute value: draw a frame around the text constant control.
<b>State:</b>	
<b>Visible</b>	VISIBLE attribute value.
<b>Enabled</b>	ENABLED attribute value.
<b>Rectangle:</b>	The following four attributes decide the text constant control's x and y axis position, its height and its width on the screen.  <b>X</b> - RECTANGLE-X attribute value. <b>Y</b> - RECTANGLE-Y attribute value. <b>W</b> - RECTANGLE-W attribute value. <b>H</b> - RECTANGLE-H attribute value.
<b>Foreground color:</b>	
<b>Selection box</b>	BACKGROUND-COLOUR-NAME attribute value.
<b>...</b>	Dialog box for editing FOREGROUND-COLOUR-VALUE attribute value.
<b>Background color:</b>	
<b>Selection box</b>	BACKGROUND-COLOUR-NAME attribute value.
<b>...</b>	Dialog box for editing BACKGROUND-COLOUR-VALUE attribute value.
<b>OK</b>	Save settings and exit the window.
<b>Cancel</b>	Exit the window without saving the settings.
<b>Help</b>	Provides online help on the attributes window.