

DTD for INatAutoNatsvar - Local Environment

Applies to INatAutoNatsvar::SystemVariables.

For the local environment, the XML document is structured according to the following DTD:

```
<?xml version="1.0" encoding="UTF-8"?>
<!ELEMENT APPLIC-ID (#PCDATA)>
<!ELEMENT APPLIC-NAME (#PCDATA)>
<!ELEMENT DEVICE (#PCDATA)>
<!ELEMENT ERROR-TA (#PCDATA)>
<!ELEMENT ETID (#PCDATA)>
<!ELEMENT GROUP (#PCDATA)>
<!ELEMENT HARDCOPY (#PCDATA)>
<!ELEMENT HARDWARE (#PCDATA)>
<!ELEMENT HOSTNAME (#PCDATA)>
<!ELEMENT INIT-ID (#PCDATA)>
<!ELEMENT INIT-PROGRAM (#PCDATA)>
<!ELEMENT INIT-USER (#PCDATA)>
<!ELEMENT LANGUAGE (#PCDATA)>
<!ELEMENT LIBRARY-ID (#PCDATA)>
<!ELEMENT MACHINE-CLASS (#PCDATA)>
<!ELEMENT NATVERS (#PCDATA)>
<!ELEMENT NET-USER (#PCDATA)>
<!ELEMENT OPSYS (#PCDATA)>
<!ELEMENT OS (#PCDATA)>
<!ELEMENT OSVERS (#PCDATA)>
<!ELEMENT PARM-USER (#PCDATA)>
<!ELEMENT PATCH-LEVEL (#PCDATA)>
<!ELEMENT PID (#PCDATA)>
<!ELEMENT SERVER-TYPE (#PCDATA)>
<!ELEMENT STARTUP (#PCDATA)>
<!ELEMENT STEPLIB (#PCDATA)>
<!ELEMENT SystemVariables (APPLIC-ID, APPLIC-NAME, DEVICE, ERROR-TA, ETID,
GROUP, HARDCOPY, HARDWARE, HOSTNAME, INIT-ID, INIT-PROGRAM, INIT-USER,
LANGUAGE, LIBRARY-ID, MACHINE-CLASS, NATVERS, NET-USER, OPSYS, OS, OSVERS,
PARM-USER, PATCH-LEVEL, PID, SERVER-TYPE, STARTUP, STEPLIB, TP, TPSYS,
TPVERS, WINMGR, UI, USER, USER-NAME, WINMGRVERS)>
<!ELEMENT TP (#PCDATA)>
<!ELEMENT TPSYS (#PCDATA)>
<!ELEMENT TPVERS (#PCDATA)>
<!ELEMENT UI (#PCDATA)>
<!ELEMENT USER (#PCDATA)>
<!ELEMENT USER-NAME (#PCDATA)>
<!ELEMENT WINMGR (#PCDATA)>
<!ELEMENT WINMGRVERS (#PCDATA)>
```