

SM-PIN* - PIN Routine Messages

This section describes the messages produced in the plug-in (PIN) modules of the error handling and message buffering facility.

Overview of Messages

SM-PINTAUTOR1 | SM-PINAUTOR2 | SM-PINAUTOR3 | SM-PINAUTOR4 |
SM-PINAUTOR5 | SM-PINAUTOR6

SM-PINTAUTOR1 File number not found in thread

Explanation An autorestart error occurred and PINAUTOR attempted to exclude the file from autorestart processing. Because the file number is not contained in the thread, it is not possible to exclude the file and the nucleus terminates.

Action Follow normal procedures for the parameter error 31 message.

SM-PINAUTOR2 Will exclude file *file-number* from autorestart

Explanation The parameter error 31 message is related to the file number indicated in the message. The file has now been excluded from autorestart processing and an attempt will be made to perform autorestart without the file.

Action An excluded file may become inconsistent and need to be restored from a backup using ADASAV RESTORE.

SM-PINAUTOR3 Maximum number of files excluded from autorestart

Explanation The maximum number of files allowed to be excluded has been exceeded.

Action Adjust the number of files allowed for exclusion in ADASMXIT and retry autorestart, or restore and regenerate your database.

SM-PINAUTOR4 File or response code invalid for exclusion

Explanation The file or response code has been specified as ineligible for exclusion in ADASMXIT.

Action Modify the ADASMXIT table to allow the response code or file and retry autorestart or follow the same recovery guidelines as for a parameter error 31.

SM-PINAUTOR5 **Not possible to exclude RSP *response-code***

Explanation The response code encountered may not be excluded

Action Follow the recovery guidelines as specified for a parameter error 31

SM-PINAUTOR6 **Cannot exclude system file**

Explanation The error relates to the checkpoint or security file. It is not possible to exclude either of these files.

Action Follow the recovery guidelines as outlined for a parameter error 31.