

DCAM Feedback Codes

Code	Explanation
0C04	Application not connected with partner. LOSCON contingency processing is probably pending.
0C40	Connection was refused by partner without reason. With TRANSIT-CD (Entire Net-Work VTAM): Line was deactivated (INACT); e.g., /DADM PX25,vr,RESET,vr1 1r7.
0C48	Time-out for connection request. With TRANSIT-CD (Entire Net-Work VTAM): Cross-domain session did not notice IPL on IBM side; e.g., /DADM PNET,vr,ACT,siehost,siepat.
0C4C	DCAM partner application not active.
0C5CXX	OPNCON was rejected by partner: <ul style="list-style-type: none"> ● 00: ● 18: Application not active on SISNIX (via HDLC). ISO=Y on X.25 link. ● 2: Partner rejects connection; partner has different information (NAME) for this application; or ISO application wanted to connect to a non-ISO application. ● 5C: Application not active via X.25; or an X.25 "call-user-data" was probably required.
0C78	Immediately after connection installation, the partner or system disconnected. ISO parameter missing.
1840	Invalid processor name: <ul style="list-style-type: none"> ● Check that the processor name is in RDDF; ● Issue a /BCIN command.
100408	BDCAM buffer shortage. DCAM driver waits for 5 seconds and retries operation. When GO signal is not used. retry is scheduled after DCAM has given the GO signal.
10040C	BDCAM buffer shortage. Wait for GO signal.