

# RDPORT - Remote Debugger Port

This Natural profile parameter specifies the port number on which a remote debugger on a Windows computer has been installed.

<b>Possible settings</b>	0 – 9999	Port number.  By default, the debugger service is installed on the Windows computer's Port 2600. You can therefore leave the UNIX computer's RDPORT setting at the default. If, however, Port 2600 on Windows has been reserved for another service, and a different port number has been specified, you must change RDPORT accordingly.
<b>Default setting</b>	2600	
<b>Dynamic specification</b>	yes	
<b>Specification within session</b>	no	

**Anmerkung:**

See the *Debugger* documentation for further details.