

# Natural Web Server Extensions - Error Messages

This section lists error messages you may receive when working with the Natural Web Server Extensions.

Error Number	Error Message	Description	User	Programmer	Administrator
NWW0001	No library and subprogram specified.	The specified URL is not correct. Names of library and subprogram are missing.	Correct the URL.	None.	None.
NWW0002	No library specified.	The specified URL is not correct.	Correct the URL.	None.	None.
NWW0003	File ... not found.	The initialization file for your adapter cannot be found.	None.	None.	Check your installation.
NWW0004	No subprogram specified.	The specified URL is not correct.	Correct the URL.	None.	None.
NWW0010	RPC call failed.	EntireX RPC cannot be initialized.	None.	None.	Check installation.
NWW0011	ERX error ... occurred ...	Internal ERX error. See EntireX Communicator documentation for further information.  If the error contains the following part:  <i>Message:</i> ... <i>Program = NATSRVD</i> ... <i>Error = 00082</i> ...  The called program does not work.	Correct URL.	Check and stow your program.	Check installation.
NWW0012	ERX error register.	EntireX RPC Service cannot be initialized.	None.	None.	Check configuration.
NWW0013	erx.dll cannot be loaded. Subcode: ....	EntireX Communicator erx.dll not found.	None.	None.	Check installation.
NWW0014	ERX logon failed.	EntireX Communicator logon cannot be performed.	Check User-ID, Password	Check installation file for Check User-ID, Password.	Check installation.
NWW0015	ERX logoff failed.	Logoff from EntireX Communicator failed.	None.	None.	Contact Software AG.
NWW0033	File ... not found (Error: ...).	The initialization file for your adapter cannot be found.	None.	None.	Check your obj.conf setup for NSAPI.
NWW0034	NWW_USER_ID too long.	User ID only with a maximum of 8 characters allowed.	None.	None.	Specify only user IDs with 8 characters or fewer, even if other system will allow more.
NWW0035	NWW_PASSWORD too long.	Passwords only with a maximum of 8 characters allowed.	None.	None.	Specify only (user-) passwords with 8 characters or fewer, even if other system will allow more.
NWW0036	Natural Library Name too long.	Natural allows only library names up to 8 characters.	Check URL.	Check URL specification.	None.

Error Number	Error Message	Description	User	Programmer	Administrator
NWW0037	Natural Subprogram Name too long.	Natural allows only Subprogram names up to 8 characters.	Check URL.	Check URL specification.	None.
NWW0099	CONTENT_TYPE: ... is not supported.	Only data with CONTENT_TYPE = application/x-www-form-urlencoded is supported.	None.	Do not use the attribute ENCTYPE at your FORM tag.	None.
NWW0100	RPC_INOUT_LENGTH is greater than 30000.	The output returned to the HTTP server is limited to restrictions of Natural RPC.  <b>Note:</b> This message does not apply to SYSWEB3.	None.	None.	Change configuration.
NWW0101	Number of parameters is greater than 200.	The input parameter given from the HTTP server is limited to 200 parameters.  <b>Note:</b> This message does not apply to SYSWEB3.	None.	Reduce number of parameters transferred to the Web Interface.	None.
NWW0200	No Header specified.	Each page needs a header section at the return page.	None.	Each page should contain a CONTENT_TYPE. The header section has to be separated from the data by a blank line.	None.
NWW0201	Page contains no Data.	Every return page has to contain data.	None.	Correct the program.	None.
NWW0815	Interface A1(1:v) no longer supported.	Wrong interface specified.	None.	None.	Remove NWW_INOUT_FORMAT and NWW_INOUT_LENGTH parameter.
NWW1001	No class and method specified.	The specified URL is not correct. Names of class and method are missing.	Correct the URL.	None.	None.
NWW1002	No class specified.	The specified URL is not correct.	Correct the URL.	None.	None.
NWW1004	No method specified.	The specified URL is not correct.	Correct the URL.	None.	None.
NWW1005	ASCII Unicode conversion failed.	The transferred data has to be converted.	None.	None.	Contact Software AG.
NWW1006	Unicode ASCII conversion failed.	The transferred data has to be converted.	None.	None.	Contact Software AG.
NWW1007	Method ... not found.	A specified method cannot be called.	Correct the URL.	Add method to your class.	Check your registry configuration.
NWW1008	Class ... not found.	A specified class cannot be called.	Correct the URL.	Create class and register with REGISTER *	Check your registry configuration.
NWW1009	Initialization of Class ... failed.	A specified class cannot be called.	Correct the URL.	Create class and register with REGISTER *	Check your registry configuration.
NWW1010	DCOM call failed, error ....	The call to DCOM failed.	None.	None.	Check your configuration.

<b>Error Number</b>	<b>Error Message</b>	<b>Description</b>	<b>User</b>	<b>Programmer</b>	<b>Administrator</b>
NWW1011	DCOM error ... occurred ...	Internal DCOM error. See DCOM documentation for further information.	Correct the URL.	Correct the program.	Correct the Configuration/Installation.
NWW1012	DCOM initialization failed.	The initial call to DCOM failed.	None.	None.	Correct the Configuration/Installation.
NWW1013	DCOM release failed.	The deletion of class and close of DCOM failed.	None.	None.	Correct the Configuration/Installation.
NWW1036	DCOM Class Name too long.	Natural allows only library names up to 32 characters.	Check the URL.	Check the URL specification.	None.
NWW1037	DCOM Method Name too long.	Natural allows only subprogram names up to 32 characters.	Check the URL.	Check the URL specification.	None.
NWW2009	Logon to Library ... failed (Error: ...).	The specified library name is not correct.	Correct the URL.	None.	None.
NWW2010	PAL call failed (Error: ...).	The call to PAL failed.	None.	None.	Check your configuration.
NWW2011	PAL error ... occurred.	Internal PAL error. See PAL documentation for further information.	Correct the URL.	Correct the program.	Correct the Configuration/Installation.
NWW2012	PAL initialization failed (Subcode: ...).	The initial call to PAL failed.	None.	None.	Correct the Configuration/Installation.
NWW2013	PAL Transport not initialized. (Subcode: ...).	Natural allows only subprogram names up to 32 characters.	Check the URL.	Check the URL specification.	None.
NWW2014	PAL Transport failed. (Subcode: ...).	Natural allows only subprogram names up to 32 characters.	Check the URL.	Check the URL specification.	None.