

# Message Class 1008 - EntireX License

This class indicates an error occurred in the evaluation of the EntireX license file. Messages of this class have the format:

1008nnnn

where 1008 is the message class, and

nnnn is the message number in the range 0000 - 9999.

## Overview of Messages

10080001	10080002	10080003	10080004	10080005	10080006
10080007	10080008	10080010	10080012	10080013	10080014
10080015	10080016	10080017	10080018	10080019	10080020
10080021	10080022	10080023	10080024	10080025	10080026
10080027	10080028	10080029	10080030	10080031	10080032
10080033	10080034	10080035	10080036	10080037	10080038
10080081	10080082	10080083	10080099		

### **10080001      EntireX license file :1: not found**

**Explanation**    The EntireX XML license key file was not found.

**Action**            Check the filename :1:. Check that the EntireX component has read access to the EntireX license file. On UNIX, check the environment variable \$EXXDIR. If this is correct, contact Software AG support.

### **10080002      The EntireX license has expired**

**Explanation**    Your EntireX license has expired.

**Action**            Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

### **10080003      EntireX is not licensed for your operating system**

**Explanation**    Your EntireX license is not valid for your operating system.

**Action**            Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

**10080004      EntireX license file does not contain a valid key**

**Explanation**    Your EntireX XML license key file is incorrect and thus invalid.

**Action**            Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

**10080005      EntireX license file has been changed or is corrupt**

**Explanation**    Your EntireX XML license key file is incorrect and thus invalid.

**Action**            Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

**10080006              Internal error [:1:] in Software AG license interface**

**Explanation**      An internal error occurred during the EntireX license check.

**Action**              Contact Software AG support.

**10080007      EntireX license file does not contain EntireX Broker**

**Explanation**    Your EntireX XML license key file is incorrect and thus invalid.

**Action**            Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

**10080008      EntireX license file does not contain Subcomponent <:1:> in Component <:2:>**

**Explanation**    The license file does not contain the required subcomponent :1: in the section :2:.

**Action**            Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

**10080010      Unable to determine SAG\_COMMON**

**Explanation**    The environment variable \$SAG is missing. The installation would appear to be incorrect.

**Action**            Make sure that the product you are using was installed correctly. Otherwise contact Software AG support.

**10080012      EntireX license file has no entry for Version :1:**

**Explanation**    The license file does not contain the required version information.

**Action**            Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

**10080013      Price unit value of EntireX license file is not valid**

**Explanation**    z/OS: Your EntireX XML license key file is incorrect and thus invalid.

**Action**            Contact Software AG support.

**10080014      Error from QVS interface**

**Explanation**    z/OS: The query interface returned a bad return code.

**Action**            No action required.

**10080015      CPUID :1: is not defined in EntireX license file**

**Explanation**    z/OS: Your EntireX XML license key file does not contain the CPUID :1:.

**Action**            Contact Software AG support.

**10080016      LPAR name :1: is not defined in EntireX license file**

**Explanation**    z/OS: Your EntireX XML license key file does not contain the LPAR name :1:.

**Action**            Contact Software AG support.

**10080017      LPAR name is not accepted with CPU-based pricing model**

**Explanation**    z/OS: Your EntireX XML license key file is incorrect.

**Action**            The error is currently ignored.

**10080018      Machine capacity higher than MSU in EntireX license file**

**Explanation**    z/OS: Your EntireX XML license key file is incorrect.

**Action**            The error is currently ignored.

**10080019          Please check licensed MSU value :1: with SCRT Report****Explanation**          z/OS: Your EntireX XML license key file is incorrect.**Action**                  The error is currently ignored.**10080020          High Availability PStore (RUN-MODE=STANDBY) not licensed****Explanation**          This license option for this feature is missing.**Action**                  Contact Software AG support.**10080021          CPUID :1: is not defined in EntireX license file. It is therefore assumed that you are running in a Disaster Recovery environment****Explanation**          z/OS: Your EntireX XML license key file does not contain the CPUID :1:.**Action**                  Contact Software AG support.**10080022          Not running in a VM****Explanation**          EntireX is not running in a virtual machine.**Action**                  Request a new license to run EntireX in a non-VM environment.**10080023          Error during VM determination****Explanation**          An internal error occurred during determination of virtual machine.**Action**                  Contact Software AG support.**10080024          Present CPU is in a higher performance bucket than licensed****Explanation**          The performance bucket in the license key file does not match the CPU of the machine.**Action**                  Contact Software AG support to request an upgrade of the license key file.**10080025          Error during determination of bucket****Explanation**          An internal error occurred during determination of the bucket.**Action**                  Contact Software AG support.

<b>10080026</b>	<b>Error during determination of CPU model</b>
<b>Explanation</b>	An internal error occurred during determination of the CPU model.
<b>Action</b>	Contact Software AG support.
<b>10080027</b>	<b>Provided buffer is too small</b>
<b>Explanation</b>	An internal error occurred.
<b>Action</b>	Contact Software AG support.
<b>10080028</b>	<b>File read error (fread)</b>
<b>Explanation</b>	The license key file could not be read.
<b>Action</b>	Check if the license key file can be read.
<b>10080029</b>	<b>Trial License Key file must not be write-protected</b>
<b>Explanation</b>	The license key file cannot be modified.
<b>Action</b>	Check the file attributes of the license key file. Set it to writable.
<b>10080030</b>	<b>ASCII-to-EBCDIC (or vice versa) conversion error occurred</b>
<b>Explanation</b>	An internal error occurred during conversion of the license data.
<b>Action</b>	Check if the correct license file was used.
<b>10080031</b>	<b>UTF Conversion Source exhausted</b>
<b>Explanation</b>	An internal error occurred during conversion of the license data.
<b>Action</b>	Contact Software AG support.
<b>10080032</b>	<b>UTF Conversion Target exhausted</b>
<b>Explanation</b>	An internal error occurred during conversion of the license data.
<b>Action</b>	Contact Software AG support.

**10080033 File write error (fwrite)**

**Explanation** The license key file cannot be modified.

**Action** Check if write permission is missing or if no space is available.

**10080034 GetVersion() failed**

**Explanation** An internal error occurred.

**Action** Contact Software AG support.

**10080035 File read error (fseek)**

**Explanation** The license key file is corrupted and cannot be read.

**Action** Contact Software AG support.

**10080036 Number of physical CPUs present exceeded**

**Explanation** The license key file does not reflect the actual number of physical CPUs.

**Action** Contact Software AG support to request an upgrade of the license key file.

**10080037 Determination of number of CPUs failed**

**Explanation** An internal error occurred during determination of the number of CPUs.

**Action** Contact Software AG support.

**10080038 Virtualized environment not included in your product license**

**Explanation** EntireX is running in a virtual machine without being licensed.

**Action** Request a new license to run EntireX in a VM environment.

**10080081 The EntireX Adapter license key file does not contain a license for connections to IMS Connect**

**Explanation** This license option for this feature is missing.

**Action** Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

**10080082      The EntireX Adapter license key file does not contain a license for connections to CICS ECI**

**Explanation**    This license option for this feature is missing.

**Action**            Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

**10080083      The EntireX Adapter license key file does not contain a license for connections to Direct RPC**

**Explanation**    This license option for this feature is missing.

**Action**            Enter a valid license file on the EntireX Installation preference page or contact Software AG support.

**10080099      Component EntireXBroker without Broker Yes**

**Explanation**    Broker is not authorized to run. Only the Administration Service with RUN-MODE=ADMIN can be started with this license file.

**Action**            If you want to run a broker other than the Administration Service, contact Software AG support.