

NEWWORK: Defining a Work File

The following parameters are used for Work data set definition:

```
ADADEF NEWWORK WORKSIZE = size  
[NOUSERABEND]  
[WORKDEV = device-type-list ]
```

Notes:

1. The Adabas nucleus must not be active during this function, and the old Work must be specified in the JCL/JCS.
2. The ADADEF NEWWORK function cannot be executed if a pending autorestart exists.

This chapter covers the following topics:

- Essential Parameter
 - Optional Parameters
 - Example
-

Essential Parameter

WORKSIZE: Work Data Set Size

The number of blocks or cylinders to be assigned to the Work data set.

Optional Parameters

NOUSERABEND: Termination without Abend

When a parameter error or a functional error occurs while this utility function is running, the utility ordinarily prints an error message and terminates with user abend 34 (with a dump) or user abend 35 (without a dump). If NOUSERABEND is specified, the utility will *not* abend after printing the error message. Instead, the message "*utility* TERMINATED DUE TO ERROR CONDITION" is displayed and the utility terminates with condition code 20.

Note:

When NOUSERABEND is specified, we recommend that it be specified as the first parameter of the utility function (before all other parameters). This is necessary to ensure that its parameter error processing occurs properly.

WORKDEV: Device Type

The device type to be assigned to the new Work data set.

This parameter is required only if the device type to be used is different from that specified by the ADARUN DEVICE parameter.

Example

A new Work data set is defined with a size of 50 cylinders. The device type is obtained from the ADARUN DEVICE parameter.

```
ADADEF NEWWORK  
ADADEF WORKSIZE=50
```