9 software AG

Adabas Online System

Session Monitoring

Version 8.1.3

June 2008

Adabas Online System

This document applies to Adabas Online System Version 8.1.3 and to all subsequent releases.
Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.
Copyright © Software AG 2008. All rights reserved.
The name Software AG, webMethods and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. Other company and product names mentioned herein may be trademarks of their respective owners.

Table of Contents

1 Session Monitoring	1
2 Display Cluster Members	3
3 Maintain User Profiles	5
4 Display or Modify Parameters	11
5 Display installed products	15
6 Queue Displays	17
Display User Queue Elements	19
Display Command Queue	20
Display Hold Queue	21
7 Refresh Nucleus Statistics	23
8 Current Resource Statistics	25
Statistics for Versions of Adabas Prior to 6.2	27
Adabas Version 6.2 and Above Statistics	28
9 Maintain TCP/IP URLs	31
10 Resource Utilization	33
Command Usage	34
File Usage	35
High Water Marks	36
Work Pool (LWP) Usage	36
Nucleus File Status	37
Protection Log (PLOG) Status	38
System Status	38
Thread Usage	40
WORK Status	41
Cluster Usage	43
11 Replicator Management	51
12 Display Maintenance Levels	53
Index	55

1 Session Monitoring

This part of the documentation presents the Adabas session monitoring functions, which allow you to control and manage major Adabas resources. These functions are most useful when analyzing system performance or seeking the cause of performance problems.

Code Service Code Service	09:11:45	**** ADABAS - Session			2006-07-14 PAC0002
C Maintain user profiles S Current resource statistics D Display parameters T Maintain TCP/IP URL I Display installed products U Display resource utilization P Modify parameters V Replicator Management Q Display queues Z Display maintenance levels ? Help . Exit	Code	Service	Code	Service	
D Display parameters T Maintain TCP/IP URL I Display installed products U Display resource utilization P Modify parameters V Replicator Management Q Display queues Z Display maintenance levels ? Help . Exit	A	Display cluster members	R	Refresh nucleus sta	atistics
I Display installed products U Display resource utilization P Modify parameters V Replicator Management Q Display queues Z Display maintenance levels ? Help . Exit	C	Maintain user profiles	S	Current resource st	tatistics
<pre>P</pre>	D	Display parameters	T	Maintain TCP/IP UR	L
<pre>Q Display queues</pre>	I	Display installed products	U	Display resource ut	tilization
<pre>? Help . Exit Code Database ID 54 (ADANAT-DB) Command ==> PF1 PF2 PF3 PF4 PF6 PF7 PF8 PF12</pre>	P	Modify parameters	V	Replicator Manageme	ent
. Exit Code Code Database ID 54 (ADANAT-DB) Command ==> PF1 PF2 PF3 PF4 PF7 PF8 PF12	Q	Display queues	Z	Display maintenance	e levels
Code Database ID 54 (ADANAT-DB) Command ==> PF1 PF2 PF3 PF4 PF6 PF7 PF8 PF12	?	Help			
Database ID 54 (ADANAT-DB) Command ==> PF1 PF2 PF3 PF4 PF6 PF7 PF8 PF12	•	Exit			
Database ID 54 (ADANAT-DB) Command ==> PF1 PF2 PF3 PF4 PF6 PF7 PF8 PF12					
Database ID 54 (ADANAT-DB) Command ==> PF1 PF2 PF3 PF4 PF6 PF7 PF8 PF12					
Command ==> PF1 PF2 PF3 PF4 PF6 PF7 PF8 PF12		Code			
PF1 PF2 PF3 PF4 PF6 PF7 PF8 PF12		Database ID 54 (ADANAT	-DB)		
PF1 PF2 PF3 PF4 PF6 PF7 PF8 PF12					
PF1 PF2 PF3 PF4 PF6 PF7 PF8 PF12					
	Command	==>			
Help Exit Menu	PF1	- PF2 PF3 PF4	PF6	PF7 PF8 1	PF12
	Help	Exit		I	Menu

You can use the Session Monitoring environment to monitor the Adabas nuclei in a multiprocessing environment.

When you enter the DBID of a cluster database on the Session Monitoring menu, subsequent screens include a field to specify the ID of the nucleus (NUCID) in the cluster you want to monitor:

- If you do not set the nucleus ID, AOS defaults to the local nucleus.
- If you set the nucleus ID to zero for a cluster database, the selected function is performed for *all* active nuclei in the cluster.

The Adabas Online System Session Monitoring documentation is organized in the following topics:

	Code	Function
3	A	Display Cluster members
3	С	Maintain User Profiles
3	D/P	Display or Modify Parameters
3	I	Display Installed Products
3	Q	Queue Displays
3	R	Refresh Nucleus Statistics
3	S	Current Resouce Statistics
3	T	Maintain TCP/IP URLs
3	U	Resource Utilization
3	V	Replicator Management
•	Z	Display Maintenance Levels

2

Display Cluster Members

Selecting option "A" from the Session Monitoring menu to display cluster members produces the following screen:

10:22:45 * DBID 105		ASIC SERVICES ***** ster Members -	2006-07-14 PACA002
Total number of nuc	clei in the cluster: 4		
I Sel I Nuc ID I Sy	ystem ID I Jobname I	Status I Available	Services I
I _ I 1 I DA	AEMVS I ADANUC01 I	Active I All	I
I _ I 2 I DA	AEMVS I ADANUC02 I	Inactive I List, Cache	I
I _ I 3 I DD	DZMVS I ADANUC03 I	Active I All	I
I _ I 4 I DD	DZMVS I ADANUC04 I	Active I All	I
I I I	I I	I	I
I I I	I I	I	I
I I I	I I	I	I
I I I	I I	I	I
I I I	I I	I	I
I I I	I I	I	I
I I I	I I	I	I
I I I	I I	I	I
I I I	I I	I	I
			10
		F6 PF7 PF8	
Help	Exit Refresh		Menu

The screen displays a list of nuclei participating in the cluster and information about the current status of each nucleus.

To select a nucleus for additional processing

■ Type "S" in the Sel column opposite that nucleus.

To display additional information about a nucleus

■ Type "D" in the Sel column opposite that nucleus.

For an Adabas cluster nucleus that has a nonzero nucleus ID, its entry in the parallel participant table (PPT) is displayed in a screen similar to the following:

10:23:45	**** A D A B A S	BASIC SERVICES ****	2006-07-14
DBID 105	- Displa	ay PPT Entry -	PACA002
Nuc ID	3 Active Nucleus		
Name	Status	DataSet Name	
WORK1		SAG.ADABAS.DB105.WORKR1	
PLOGR1	Ready to be copied/merged	SAG.ADABAS.DB105.PLOGR1	
PLOGR2	Being written by nucleus	SAG.ADABAS.DB105.PLOGR2	
PF1	PF2 PF3 PF4	PF6 PF7 PF8	- PF12
Help	Exit Refresh		Menu

3 Maintain User Profiles

Adabas allows you to retain user-related information from session to session in a user profile table that includes

- ET records;
- user priority;
- user-specific timeout (TNxx, TT, and TLSCMD);
- ISN buffering (NSISN, NSISNHQ);
- command ID (NQCID) values that differ from the established ADARUN values; and
- owner ID information for multiclient files.

Selecting $\mathtt{Maintain}$ user $\mathtt{profiles}$ (option "C") from the Session Monitoring menu displays the following menu:

```
10:24:31
               **** A D A B A S BASIC SERVICES *****
                                                            2006-07-14
                        - Maintain User Profiles -
                                                              PACIC02
                 Code Service
                        List/modify user profile(s)
                   L
                   M
                        Mass function
                   X
                        Delete ETID-ranges
                         Help
                         Exit
      Code .....
      Start UID ....
      Database ID .. 105
```

```
Command ==>
PF1---- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12----
Help Exit Menu
```

From the Maintain User Profiles menu, you can

- list and modify a user profile table (option "L");
- copy a user profile to one or more other users (option "M"); and
- remove one or more ETIDs from the Adabas checkpoint file thereby deleting both profile and ET data (option "X").

If necessary, you can supply a starting user ID. If the Start UID field is left empty, Basic Services displays entries starting from the beginning of the user profile table. You can use range notation for the starting value. For example, if you enter JA* in the Start UID field, the display begins with user IDs that start with the letters "JA".

If necessary, you can change the database by overtyping the value shown.

To list and modify the user profile table

■ Enter "L" in the Code field and press ENTER.

The List/Modify User Profiles screen displays the user profile table:

You can modify existing profiles and add new user ones. For each user, you can maintain

a user priority to add "weight" to the normal, built-in priorities of Adabas commands issued by a specific user when they contend with other commands for Adabas database priority. The effect is to change the user's database access priority. An equivalent direct command is

```
<u>CH</u>ANGE <u>PR</u>IORITY
```

- nonactivity timeout values for access-only users (TNAA), ET logic users (TNAE), and EXU users (TNAX).
- transaction time limits for ET Logic users (TT).
- a time limit for executing a database query (Sx) command (TLSCMD).
- the number of ISNs allowed per TBI element (NSISN).
- the number of records that can be placed in hold status at one time (NISNHQ).
- the number of active command IDs allowed (NOCID).
- an owner ID for multiclient support.

To copy the attributes of a user profile to one or more other user profiles

■ Enter "M" in the code field and press ENTER.

On the resulting screen, you can type in the user ID of the profile to be copied, and the names of the users whose profiles are to be taken from that user ID.

In the example, users XYZ1 and XYZ2 inherit all values from user USER1 and effectively define a group.

To delete a range of user IDs

1 Enter "X" in the Code field and press ENTER.

A window opens asking whether you want to delete all user IDs or select the user IDs to be deleted:

10:37:54 **** A D	A B A S BASIC S	SERVICES ****	2006-07-14
	Maintain User Pr	rofiles -	PACIC02
Codo	Commisso		
Code	Service		
L	List/modify user	profile(s)	
_ M	Mass function	<u> </u>	
X	Delete ETID-range	es	
?	Help		
	Exit +		+
	'Y'	- Select ETIDs for	
Code x		Deletion	
Start UID ba*	'N'	- Delete ETIDs with	NO
Database ID 105	(RD-105)	Selection	
		<==== Select Option	n
	'	Help PF3=Exit	
Command ==>	'		· ·
PF1 PF2 PF3	PF4 PF6	PF7 PF8	
Help Exit			Menu

- **Caution:** Be careful about answering "N" (No) to the prompt. You could inadvertently delete IDs that you want to keep.
- 2 If you enter "N" (No) in the window's Select Option field, Basic Services deletes all user IDs in the specified range with "no" confirmation.

If you answer "Y" (Yes, the default), the Mass Delete of ET-IDs screen is displayed so that specific ETIDs may be marked for retention:

10:40:33	**** A D	A B A S	BASIC SERV	ICES ****	2006	-07-14
DBID 105	-	- Mass De	lete of ET-	IDs -	P.	ACICD2
Delete all ET	'-IDs start	ing with Use	erid = BA*			
All entries	marked 'K'	(Keep) wil.	I NOT be	e deleted.		
Userid	Userid	Userid	Userid	Userid	Userid	Userid
BABRAB	BABRAN	BACANT	BADBEE	BADFUE	BADKED	BADKHK
				_		
BADNTU	BADTCS	BADWAT	BAFCKA	BAFJVS	BAGDTS	BAGJAR
BAGJKI	BAGJVN	BAGKIT	BAGLAW	BAGNET	BAGPCT	BAGPCP
BAGPCR	BAGPST	BAGSIR	BAGSWI	BAGTUF	BAGTON	BAGZAP
BAHNAK	BAJLOB	BAJPJS	BAKLIM	BAKSAT	BAMCID	BAMLIP

BAMLOT	BAMPCS	BAPEHN	BAPLAB	BARHEN	BARHER	BASHEP
BASMOR	BASWAN	BASWIG				

As indicated in the message on the screen, you need to mark with "k" those user IDs that you want to *keep*. Unmarked user IDs will be deleted when you press ENTER.

Note: When a user ID is deleted, both the user profile and any ET data for the user are deleted.

You can leave the screen without deleting any user IDs by using the EXIT key PF3.

4 Display or Modify Parameters

To view Adabas nucleus (ADARUN) parameters

■ Choose option "D" from the Session Monitoring menu and press ENTER.

The equivalent direct command is

```
DBID 1955
                           - Display Parameters
                                                                 PACP002
Modify parameters below, as required:
----- Miscellaneous -----
                                    ----- User Specific Limits -----
ReadOnly session (READONLY) .. NO
                                    Hold Queue Limit (NISNHQ) .. 2000
UTI only session (UTIONLY) .. NO
                                   CIDs per User
                                                      (NQCID) .. 40
OPEN required
                  (OPENRQ) .. NO
                                    ISNs / TBI Element (NSISN) .. 1000
Ignore DIB Entry (IGNDIB) .. NO
                                    ----- Buffer Pool -----
Local nucleus
                  (LOCAL) .. NO
                                    Bufferflush Dur. (TFLUSH) .. 1
                      (NT) .. 5
Number of Threads
                                    Parallel LFIOP I/O (FMXIO) .. 1
Non DE Search
                   (NONDES) .. YES
                                    Async. by Vol-Ser (ASYTVS) .. YES
                                    ----- Replication -----
Log AOS/DBS Update (AOSLOG) .. NO
                                    Replication (REPLICATION) ... YES
Batch Support
               (BATCH) .. NO
Data Protection Area
                     (LP) .. 1000
Ignore Work Part 4 (IGNTPC) .. NO
WORK-Part-4 Area
                   (LDTP) .. 0
WORK-Part-2 Area
                   (LWKP2) .. 104
SVC
                     (SVC) .. 249
                                                             Page 1 of 3
PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
Help
                 Exit
                                                              Menu
```

To modify Adabas nucleus (ADARUN) parameters

■ Choose option "P" from the Session Monitoring menu and press ENTER.

Modifiable values are highlighted (intensified) on the displays.

The equivalent direct command is

```
MODIFY PARAMETERS
```

Three screens are used for displaying and modifying parameters:

```
***** A D A B A S BASIC SERVICES ***** 2006-07-14
10:53:03
   DBID 105
                                  - Modify Parameters -
                                                                               PACP002
   Modify parameters below, as required:
   ----- Pools -----
                                              ----- Queues -----

      Sort Area
      (LS) .. 19968
      Command Queue
      (NC) .. 100

      Int. User Buffer
      (LU) .. 65535
      Hold Queue
      (NH) .. 9000

                                             Hold Queue
                                                                         (NH) .. 9000
                                             User Queue
   Buffer Pool (LBP) .. 127936
                                                                       (NU) .. 700
   Format Pool
                     (LFP) .. 12002
                                             ----- Time Windows -----
  ISN List Table (LI) . 10000 Transaction Time (TT) . 300
Seq. Cmd. Table (LQ) . 2500 Max Transaction Time (MXTT) . 3600
Work Pool (LWP) . 500000 Nonactivity ACC-User (TNAA) . 300
Attached Buffer (NAB) . 35 Nonactivity ET-User (TNAE) . 300
                                            Nonactivity EXU-User (TNAX) .. 300
   Security Pool (LCP) .. 10000
   UQ-DE Pool (LDEUQP) .. 5000
                                             Max Nonactivity Time(MXTNA) .. 3600
                                               Time Limit Sx-Cmds (TLSCMD) .. 286
   Flush I/O Pool (LFIOP) .. 125000
                                               Max Time for Sx-Cmds(MXTSX) .. 3600
   Err. Recovery (MSGBUFF) .. 0
                                               Command Time (CT) .. 9000
                                               SYNS60 Interval (INTNAS) .. 3600
                                                                            Page 2 of 3
  PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
                       Exit
  Help
                                                                             Menu
```

```
Modify parameters below, as required:
  ---- Command Logging ---- Protection Logging -----
  Command Logging .. YES
                        PLOG required (PLOGRQ) .. YES
  LOGCB ..... YES
                         DUAL PLOG Size
                                         (DUALPLS) .. 240
  LOGFB ..... YES
                         DUAL PLOG Device (DUALPLD) .. 3380
  LOGRB ..... YES
                         Number of PLOGs ..... 0
                          ----- Other Services -----
  LOGSB ..... NO
  LOGVB ..... NO
                          Triggers and Procedures (SPT) .. NO
  LOGIB ..... NO
                         Delta Save Facility (DSF) .. NO
  LOGIO ..... NO
                          Cache Facility (CACHE) .. YES
                          Transaction Manager (ATM) .. NO
  LOGUX ..... NO
                          TCP/IP Support (TCPIP) .. NO
  LOGSIZE ..... 4820
                          Ext. Error Recovery (SMGT) .. YES
  DUAL CLOG Size ... 675
  DUAL CLOG Dev. ... 3380 2 Phase Commit Support (DTP) .. NO
```

CLOGMRG	NO	Review	Support	(REV	7IEW)	LOCAL	
Number of CI	LOGs 0						
						Page 3	of 3
PF1 PF2-	PF3	PF4	PF6	PF7	PF8	- PF12	
Help	Exit			-		Menu	

5

Display installed products

Display"installed products" (option "I") from the Session Monitoring menu displays the following menu:

15:01:35	**** A D A B A S	BASIC SERVICES *	**** 20	005-11-18
DBid 1954	- Display Insta	alled Products -	P.A	CIIO2
	NO		Recovery	
Cluster Service	es NO	Stored Procedur	es & Triggers	NO
Parallel Service	ces NO	Two Phase Commi	t	NO
Fastpath	NO	TCPIP support .		NO
Vista	NO	Event Replicato	r	YES
Transaction Mar	nager NO			
SAF Security In	nterface NO			
Review	NO			
Adabas Online S	System YES			
Command ==>				

This screen displays what is installed on the current selected Adabas

6 Queue Displays

Display User Queue Elements	19
Display Command Queue	20
Display Hold Queue	21

Selecting "Queue displays" (option "Q") from the Session Monitoring menu displays the following menu:

```
A D A B A S BASIC SERVICES *****
11:27:20
                                                            2006-07-14
                                                              PACQ002
                           - Queue Displays -
                      Code Service
                           Display User Queue Elements
                           Display Command Queue
                           Display Hold Queue
                       H
                       ?
                           Help
                           Exit
    Max No. Elements ... 100
    Last Activity ..... 0
                               (elapsed time in seconds)
    Selection Criteria
      ET-ID (User-ID) .. _____
                               User Type ... __
      Job Name ..... ___
      Terminal ID ....._
    Database ID ..... 105
                                (RD-105)
 Command ==>
 PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
        Exit
                           Clear UID
 Help
                                                             Menu
```

The Display Queues function shows, in table format, the contents of the user, command or hold queues. Each displayed table entry contains a related TID, job name, user ID, current status, and related information such as files currently in use and command type.

If you try to display a queue that is currently empty, an appropriate message appears on the Display Queues menu.

Individual entries in the selected queues can be displayed to provide more detailed information, or selected for a later Basic Services function (the individual user-level statistics sampling described in section *Current Resource Statistics* is an example).

This chapter covers the following topics:

Display User Queue Elements

If you select Display User Queue Elements (option "A") from the Queue Displays menu, you must also specify the maximum number of elements to display. Other selection criteria you may optionally specify include

- number of seconds since last activity
- logical user ID (ETID)
- type of user (ACC, AOS, ET, EXU, EXF, UTI)
- job name
- terminal ID; and
- database ID

If multiple selection criteria are specified, they are combined with a logical OR.

11:40:48 *** DBID 105 SEL-CRIT: MAX-NUM	- Display			
	Total User:	s 3		
Mark entries with	n 'D' (Display) or '	S' (Select):		
I I	I	I User I	I Last I	I
M I TID I	ET-ID I Job Name	I Type I Status	I Activity I F	ile(s) I
_ I BANLW 1 I B	BANLW I COMPLETE			
I BARAW 1 I B	BARAW I COMPLETE	I ET I ET	I 2361 I 50	0,100 I
I BASMA 1 I B	BASMA I COMPLETE	I ET I ET	I 135 I 10	00 I
I I	I	I I	I I	I
I I	I	I I	I I	I
I I	I	I I	I I	I
I I	I	I I	I I	I
I I	I	I I	I I	I
I I	I	I I	I I	I
I I	I	I I	I I	I
PF1 PF2	PF3 PF4	PF6 PF7	PF8 PI	F12
Help	Exit Refresh	-	+ Me	enu

The equivalent display direct commands are

```
<u>DI</u>SPLAY <u>UQ</u> (user queue)
```

If you choose to display (D) an individual user ID, a user queue element information screen similar to the following appears:

```
***** A D A B A S BASIC SERVICES *****
11:44:18
                                                            2006-07-14
  DBID 105
                      - Display User Queue Element -
                                                               PACQA12
            I
                           I User I I Last
                      Ι
           I User ID I Job Name I Type I Status I Activity I lator I
                      I DCOMPLET I AOS I
  I BANLW 1 I BANLW
  Global Uid= 5203405496720001 40404040404040 00FB1900 E2C1C7D3E64040F1
  Hold Queue Limit ..... 1500
  Max. parallel CIDs per User . 100
                                       Start Times
                                       Session ..... 2006-07-14 11:04:28
  Max. ISNs per TBI Element ... 51
  Max. Time of Nonactivity .... 3775
                                       Transaction .. 0000-00-00
  Max. Transaction Time ..... 0
  Time Limit for Sx Commands .. 315
                                      File List
  No. of ISNs currently held .. 0
                                         19,100,110
  No. of CIDs currently in use: 1
  No. of Calls ..... 105
  No. of I/Os ..... 74
  Priority from ET/CP File .... 0
 PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
 Help
                  Exit
                                                             Menu
```

Display Command Queue

If you choose Display Command Queue (option "C") from the Queue Displays menu, the current commands in the com"time-in"mand queue and their status are listed. PF2 allows you to switch the display between and "jobname".

The equivalent display direct command is

<u>DI</u> SPLAY <u>CO</u>								
12:03:38	****	ADABAS				*	2006-	
DBID 10	5	- Disp	olay Comma	nd Queue	9 -		PA	CQC02
Mark en	tries with 'S	' to select	:					
MI	rid i Job	name I Cmo	l. Status	I Pr	rtyI Fnr	. I Cr	nd I Cm	d.Seq.Nr
I BAI	NLW 1 I COMP	LETE I In Pi	cocess	I 9	93 I	ΙŢ	JC I	2712
I	I	I		I	I	I	I	
I	I	I		I	I	I	I	
I	I	I		I	I	I	I	
I	I	I		I	I	I	I	
I	I	I		I	I	I	I	

I	I	I		I	-	I	I	I
I	I	I		I	-	I	I	I
I	I	I		I		I	I	I
I	I	I		I		I	I	I
PF1	PF2	PF3	PF4	PF6	PF7-	I	PF8	PF12
Help	T-in/Jobn	Exit	Refresh		_	4	+	Menu

Display Hold Queue

If you choose Display Hold Queue (option "H") from the Queue Displays menu, a list of the ISNs currently in hold status is displayed.

The equivalent display direct command is

<u>DI</u>SPLAY <u>HQ</u>

7

Refresh Nucleus Statistics

Selecting Refresh Nucleus Statistics (option "R") from the Session Monitoring menu displays the following screen:

To select the statistics to be refreshed, place an "X" in the space provided.

More than one statistic may be refreshed at the same time. The statistics selected are reset to zero.

PF3 cancels the request and returns to the Session Monitoring screen. PF12 cancels the request and returns to the AOS Main Menu.

8 Current Resource Statistics

Statistics for Versions of Adabas Prior to 6.2	. 2
Adabas Version 6.2 and Above Statistics	. 28

Selecting Current Resource Statistics (option "S") from the Session Monitoring menu invokes the Resource Statistics menu:

```
13:07:40
                    A D A B A S BASIC SERVICES *****
                                                           2006-07-14
                        - Resource Statistics -
                                                            PACS002
                   Code Service
                    G
                        Start General Statistics
                        Read General Statistics
                    S Read User Statistics
                        Start User Statistics
                        Help
                        Exit
      Code .....
      Duration .... 60 seconds
      User ID .....
      Database ID .. 105 (RD-MPM105)
 Command ==>
 PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
                          Clear UID
 Help Disp UQ Exit
                                                            Menu
```

Resource statistics provide information about file and command use either for a single user (user statistics) or for all currently active users (general statistics). The statistics must first be collected by starting a sampling period for which you have specified a time period in seconds (duration).

To obtain statistics for all currently active users

Start general statistics (option "G") and, after the specified duration, read them (option "R").

The equivalent direct commands are

```
START STATISTICS
READ STATISTICS
```

If user statistics are started (option "U") or subsequently read (option "S"), a user ID must either be indicated on this screen or have been previously selected in the Display User Queue (PF2) or Display Command Queue options; see section *Direct Commands*. PF4 is used to deselect a previously selected user ID.

This chapter covers the following topics:

Statistics for Versions of Adabas Prior to 6.2

For versions of Adabas prior to 6.2, the following resource statistics information is displayed for specific users:

```
DBID 105
                  - User Statistics -
                                          PACSS02
 Statistic Start Time ... 2006-07-14 13:21:39
 User-ID ..... SAGNA
 Threadtime: 59.6 msec. I/Os: 0 Cmds.: 142 (99.3 %)
 Command Usage : A1/4 = 33 BT =
                                   CL
                                 2 L1/4
           ET =
                     1 E1/4 =
           L2/5 =
                                 68 L9
                       L3/6 =
            LF =
                                  2 OP
                       N1/2 =
            UC =
                       RC =
                                 30 RE
            REST =
                       S1/4 =
                                 6 S2
            S5 =
                       S8 =
                                   S9
 File Usage: F-0=31 F-50=1 F-100=109 F-110=1
 PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
 Help
            Exit
                                         Menu
```

and for all currently active users (general statistics):

```
13:41:52
          **** A D A B A S BASIC SERVICES **** 2006-07-14
 DBID 105
                   - User Statistics -
                                            PACSS02
                   33 BT =
 Command Usage : A1/4 =
                                      CL
                                   2 L1/4
            ET =
                      1 E1/4 =
                                   68 L9
            L2/5 =
                        L3/6
                              =
            LF =
                        N1/2 =
                                    2 OP
            UC =
                         RC =
                                   30 RE
            REST
                =
                         S1/4 =
                                    6 S2
                         S8 =
            S5 =
                                      S9
 File Usage: F-0=31 F-50=1 F-100=109 F-110=1
```

```
PF1---- PF2----- PF3----- PF4----- PF6---- PF7---- PF8---- PF12----
Help Exit Menu
```

Adabas Version 6.2 and Above Statistics

For Adabas version 6.2 and above, two screens of statistics are displayed: the first shows command usage and the second shows file usage. You can use PF4 to toggle between the two screens.

Command Usage Display

The following command usage information is displayed for specific users:

```
**** A D A B A S
13:43:40
                                  BASIC SERVICES *****
                                                              2006-07-14
  DBID 105
                     - User Statistics: Command Usage -
                                                                PACSS12
  Statistic Start Time ..... 2006-07-14 13:10:55
                                                       UserID ... SAGNA
  L1/4 - Read/Get Record ...
                                       A1/A4 - Record Update ....
  L2/5 - Read Physical .....
                                       N1/N2 - Add Record ......
                              232 E1/E2 - Delete Record ....
  L3/6 - Read Logical .....
     - Read Descriptor ...
                                73
      - Read Field Def. ...
                                 8
                                        OP
                                              - Open User Sess ...
  LF
  RE
       - Read ET Data .....
                                        CL
                                              - Close User Sess ..
                                3
  S1/4 - Find Records .....
                                      ET - End Transaction ...
  S2
      - Find Sorted .....
                                        BT
                                              - Backout Tran. ....
  S5
       - Find Coupled ISN ..
                                        RC
                                              - Release Cmd ID ...
                                                                       254
  S8
       - Process ISN List ..
                                       UC
                                              - Utility Command ...
       - Sort ISN List .....
  S9
                                              - All other cmds ...
  Thread Time (msec) ..... 672.6
                                  99.8% User's commands ..
                                                                        562
  No. of I/Os ..... 216
                                                Total Commands ...
                                                                        563
 Command ==>
 PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
                   Exit
          GStat
                            File
                                                              Menu
```

and for all currently active users (general statistics):

```
***** A D A B A S BASIC SERVICES **** 2006-07-14
13:53:40
  DBID 105
                     - User Statistics: Command Usage -
                                                                 PACSS12
  Statistic Start Time ..... 2006-07-14 13:10:55
  L1/4 - Read/Get Record ...
                                         A1/A4 - Record Update ....
  L2/5 - Read Physical .....
                                         N1/N2 - Add Record ......
  L3/6 - Read Logical .....
                                232
                                        E1/E2 - Delete Record ....
  L9
       - Read Descriptor ...
                                  73
  LF
       - Read Field Def. ...
                                   8
                                         OP
                                               - Open User Sess ...
     - Read ET Data .....
                                               - Close User Sess ..
```

```
S1/4 - Find Records .....
                            3 ET
                                         - End Transaction ..
S2 - Find Sorted ......
                                    BT
                                         - Backout Tran. ....
S5 - Find Coupled ISN ..
                                  RC
                                                                254
                                        - Release Cmd ID ...
S8 - Process ISN List ..
                                  UC - Utility Command ..
                                   * *
S9 - Sort ISN List .....
                                         - All other cmds ...
Command ==>
PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
Help GStat Exit File
```

You can use PF2 to toggle between user statistics screens and general statistics screens whenever both have been started and are available for viewing.

File Usage Display

The following file usage information is displayed for specific users:

```
DBID 105
                  - User Statistic: File Usage -
                                                    PACSS12
  Statistic Start Time ..... 2006-07-14 14:10:55 UserID ... SAGNA
  Thread Time (msec) ..... 672.6
                                            No. I/Os.. 216
  File File Name
                  No. Cmds File File Name
  ---- ------- ------- ------ -----
     0 *Cmds with no Fnr*
8 TEST-8
   0 *Cmds with no Fnr* 90 4 EMPLOYEES
8 TEST-8 4 12 TRIGGER-FILE
100 NATURAL-FNAT 343 110 NATURAL-FDIC
                                                           52
                                                          36
     Perc of all cmds .. 99.8%
                            Commands processed:
                                                          562
 Command ==>
 PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
 Help GStat Exit Cmds
```

and for all currently active users (general statistics):

14:21:40 *****	ADABAS BAS	SIC SERVICE	ES ****	2006-07-14
DBID 105	- User Statist	ic: File Us	sage -	PACSS12
Statistic Start Time	2006-07-14	14:16:25		
File File Name	No Cmds	File Fi	ile Name	No. Cmds
0 *Cmds with no 1	Fnr* 90	4 EM	MPLOYEES	37
8 TEST-8	4	12 TF	RIGGER-FILE	52
100 NATURAL-FNAT	343	110 NA	ATURAL-FDIC	36
		Con	mmands processed	: 562
			-	
Command ==>				
PF1 PF2 PF3	PF4	PF6 PF	F7 PF8	PF12
Help GStat Exit	t Cmds			Menu

You can use PF2 to toggle between user statistics screens and general statistics screens whenever both have been started and are available for viewing.

9 Maintain TCP/IP URLs



Note: This function is available only for Adabas version 7 or above databases.

Selecting "Maintain TCP/IP URL" (option "T") from the Session Monitoring menu invokes the Display/Maintain URL screen:

```
14:33:42
               **** A D A B A S
                                   BASIC SERVICES *****
                                                              2006-07-14
DBID 105
                        - Display/Maintain URL -
                                                              PACTC02
Mark entries with 'O' to Open or 'C' to Close a URL:
               Μ
                          URL
                                        Status
                                                 Message
                                        -----
                   HPS://TCPIPMVS:1962_
                                        Closed
                   HPS://TCPIPMVS:1963_
                                        Open
                   HPS://TCPIPMVS:1964_
                                        Open
                 HPS://TCPIPMVS:1965_
                                        Open
Command ===>
PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
Help
                  Exit
                           Refr
```

The screen displays a list of all defined URLs and their current status: open or closed.

You may change the status by entering "O" to open or "C" to close in the "M" column next to the URL entry.

You may define a new URL and open it using the blank line provided at the end of the URL list.

Once you have made your changes, press PF4 (Refr) to refresh the list.

10 Resource Utilization

Command Usage	34
File Usage	
High Water Marks	36
■ Work Pool (LWP) Usage	
Nucleus File Status	37
■ Protection Log (PLOG) Status	38
System Status	
■ Thread Usage	40
WORK Status	41
■ Cluster Usage	43

Selecting Resource Utilization (option "U") from the Session Monitoring menu invokes the Resource Utilization menu:

```
14:42:51
               **** A D A B A S BASIC SERVICES *****
                                                         2006-07-14
                                                         PACU002
                    - Resource Utilization -
Code Service
                                 Code Service
  Command usage
                                  P PLOG status
С
F File usage
                                 S System status
H High water marks (pools/queues) T Thread usage
  Workpool (LWP) usage W WORK status
N Nucleus File Status
                                X Cluster usage
? Help
    Exit
      Code ..... _
      File Number .. 0
      Database ID .. 1955 (WIS1955) NucID .. 1022
Command ==>
PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
               Exit
                                                       Menu
```

The resource utilization displays provide a comprehensive overview of Adabas operation.

Each of the resource utilization options contain a refresh capability (PF4) that allows you to refresh the displayed values, a convenience for long-term monitoring of Adabas system functions.

This chapter covers the following topics:

Command Usage

Overall Command Usage (option "C") displays the total and average execution time of each Adabas command type issued during the current session and processed by the Adabas nucleus, and the total of all Adabas commands issued.

The equivalent direct command is

```
<u>DI</u>SPLAY <u>CM</u>DUSAGE
```

14:44:36 * DBID 105	**** A D A	B A S		SERVICE age -	ES ***	**		6-07-3	
		00		<u></u>				211000	_
Total Commands	19051								
CMD-Type I Nr.	CMDs I Ave	er. Dur.	I C	MD-Type	I Nr.	CMDs	I Aver.	Dur.	I
A1/4 I	592 I	0.7	 I	 ВТ	I	5	 I		I
CL I	1 I	49.3	I	ET	I	75	I		I
E1/4 I	119 I	7.4	I	L1/4	I	1570	I	1.1	I
L2/5 I	I		I	L3/6	I	9842	I	6.7	I
L9 I	473 I	2.3	I	LF	I		I		I
N1/2 I	204 I	10.3	I	OP	I	10	I	74.2	I
UC I	70 I	11.3	I	RC	I	5732	I		I
RE I	I		I	REST	I	38	I		I
S1/4 I	320 I	21.0	I	S2	I		I		I
S5 I	I		I	S8	I		I		I
S9 I	I		I						

File Usage

Overall File Usage (option "F") displays all files of the database used during the session and the number of accesses to each file.

The equivalent direct command is

```
DISPLAY FILUSAGE
            **** A D A B A S
                           BASIC SERVICES ****
14:45:31
                                                  2006-07-14
 DBID 105
                       - File Usage
                                                  PACUF12
  Fnr I Tot. Cmds Fnr I Tot. Cmds Fnr I Tot. Cmds
    0 I
                 9 I 345
                               17 I 24
                                              50 I
           5898
                                                      62
   100 I
           7939
                 101 I
                         4752
                               110 I
```

If a file number other than zero is specified on the Resource Utilization menu, the File Usage display shows file use information for the specified file:

```
14:53:02
             ***** A D A B A S BASIC SERVICES *****
                                                     2006-07-14
 DBID 105
                        - File Usage
                                                      PACUF02
  Usage Numbers for File 100 : ACC Users .. 1
                                            EXU Users ..
                             UPD Users ..
                                              UTI Users ..
                  -- USERS --
           TID/User Jobname
                            CPU-ID
                                      VM-ID
                                              Open Mode
           EXF UTI EXU
```

```
Mark entry with a 'S' to select a User

Total Users in this list for this file is 1

Page 1 of 1
```

High Water Marks

High Water Marks (option "H") displays the maximum percent of use of selected pools and queues in the current session, and the date and time when the high point was reached.

Values are displayed for the user, command, and hold queues; the ISN list and sequential command tables; the format and work pools; and the attached buffers (NAB).

These values are a good starting point when looking for a problem with limited buffer, pool, or queue space, or if you are looking for unused storage resources.

The equivalent direct command is

```
<u>DI</u>SPLAY <u>HWM</u>
```

15:55:18 DBID 105	****	* A	D A B A :	_	BASIC SER Water Mark		LCES	***	2006-07-14 PACUH02	
Pool / Queue		I 	Size	I 	Used	I	%Used	I Date	Time	I
Attached Buffer	(NAB)	I	204800	I	12032	I	5.8	I		I
Command Queue	(NC)	I	34560	I	384	I	1.1	I 2006-07-	14 14:55:06	I
Format Pool	(LFP)	I	80000	I	4364	Ι	5.4	I 2006-07-	14 14:25:23	I
Hold Queue	(NH)	I	350056	I	1736	I	0.4	I 2006-07-	14 14:46:04	I
ISN-List Table	(LI)	I	50000	I	0	I	0.0	I		I
Seq. Cmd. Table	(LQ)	I	32000	I	440	Ι	1.3	I 2006-07-	14 08:00:01	I
User Queue	(NU)	I	58644	I	2524	Ι	4.3	I 2006-07-	14 14:44:26	I
Work Pool	(LWP)	I	250000	I	92256	I	36.9	I 2006-07-	14 14:29:33	I

Work Pool (LWP) Usage

Work Pool (LWP) Usage (option "L") displays the length of the used and unused parts of the work pool as well as the length of the longest single unused part. These numbers can be used to tune the work pool length for the next session.

The equivalent direct command is

```
DISPLAY LWPUSAGE
```

Nucleus File Status

Nucleus File Status (option "N") is the equivalent of the DNFV operator command.

```
16:09:17
               **** A D A B A S BASIC SERVICES *****
                                                            2006-07-14
DBID 1955
                   - Nucleus File Status -
                                                            PACUN02
NucID 1021
         Locking
     File
         NucID Access count Update count
     24
                                        0 Access
     25
                           0
                                       0 Access, Update
Last page
PF1---- PF2---- PF3---- PF4---- PF7---- PF8---- PF9----- PF12----
Help Repos Exit Refresh -
```

In an Adabas cluster environment, the file may be locked for exclusive use by another cluster nucleus. If this is the case and the file is in the nucleus file status table, the Locking NucID column for the file shows the ID of the nucleus that has exclusive control.

The Access count / Update count fields display the number of access or update users, respectively, that refer to the specified file in their user queue elements (UQEs). These users either have specified the file in an OP command with "R"-option or are using the file in an as yet incomplete transaction.

A State field indicates when the file is used for access only or for access and update. The State field indicates to what extent a nucleus can use a file on its own. If the requested use exceeds the

given state, the nucleus must first communicate with the other nuclei in the cluster in order to upgrade the state.

Protection Log (PLOG) Status

Protection Log (PLOG) Status (option "P") displays the status of dual protection logs, if used.

The equivalent direct command is

```
DISPLAY <u>PLOGST</u>ATUS
```

```
16:16:37 ***** A D A B A S BASIC SERVICES ***** 2006-07-14
DBID 105 - PLOG Status - PACUP02

The nucleus is currently writing on .... 1
Size of one PLOG area (in BLKs.) ..... 40
Last block written ..... 25 ( 62 %)
Number of switches since nucleus start .. 10
Date/Time of last switch ..... 2006-07-14 10:31:12
```

System Status

System Status (option "S") displays I/O counts for the ASSO, DATA, WORK, and PLOG datasets; remote and local call distribution; and other current session status information.



Note: For Adabas 7.4 and above, "Logical Reads" can now display up to 23 digits; "Logical Reads (binary)" has been discarded.

The equivalent direct command is

<u>DI</u>SPLAY <u>SY</u>STEMSTATUS

16:20:16	**** A	DABASI	BASIC SERVICES ****	2006-07-14
DBID 1955		- Syste	em Status -	PACUS02
NucID: 1022				
	Physica	.1		
	Reads	Writes	Call Distribution	n
-				
ASSO	370	67	Remote Logical	. 0
DATA	3	18	Remote Physical	. 0
WORK	2	104	Local Logical	. 860
PLOG		67	Local Physical	. 0
Logical Rea	ads:			
Buffer Effi	iciency	0.9	No. of HQEs active	. 0

		No. of UQEs in User Queue	2
Format Translations	51	No. of CQEs waiting in CQ	0
Format Overwrites	0		
		Total intern. Autorestarts .	0
Throw Backs for ISN	0	No. of PLOG switches	0
Throw Backs for Space.	0	No. of Bufferflushes	18
		page 1 of 2	
PF1 PF2 PF3	PF4	PF6 PF7 PF8 PF12	
Help Exit	Refresh	+ Menu	

If you are running Adabas version 8.1, press PF8 to display an additional screen that indicates if one or more of the following are in progress:

- Online database save running;
- ADAEND in progress;
- Online file save running;
- READONLY/UTIONLY transition;
- READONLY status;
- Update processing suspended;
- ET-sync in progress;
- UTIONLY status; and
- Exclusive-DB-control utility running.

Otherwise, "Adabas operation normal" is displayed.

16:37:41	**** A D A B A S BASIC SERVICES ****	2006-07-14
DBID 1955	- System Status -	PACUS02
NucID: 1021		
	Nucleus Status Flags	
	Adabas operation normal	
	page 2 c	of 2

```
PF1---- PF2----- PF3----- PF4----- PF6---- PF7---- PF8---- PF12-----
Help Exit Refresh + Menu
```

Thread Usage

Thread Usage (option "T") displays a table of all defined Adabas threads, the status of each, the command type currently in process in each active thread, and the number of commands processed by each thread in the current session.

The equivalent direct command is

<u>DI</u> SPLAY <u>TH</u> READUSAGE

16:54:21 ***** A	DABAS BASIC - Thread Usag		2006-07-14 PACUT02
Nr. I Thread Status	I Command Type	I Wait Event	I Nr. CMDs I
1 I Waiting for event	I Update	I Queued Event	I 39327 I
2 I Waiting for event	I Update	I I/O	I 19228 I
3 I Waiting for event	I Update	I I/O	I 16170 I
4 I Waiting for event	I Update	I Async Work I/O	I 14376 I
5 I Waiting for event	I Update	I Queued Event	I 13205 I
6 I Waiting for event	I Update	I Async Work I/O	I 10461 I
7 I Waiting for event	I Update	I PLOG I/O	I 9872 I
8 I Waiting for event	I Update	I Queued Event	I 9904 I
9 I Waiting for event	I Update	I Queued Event	I 8233 I
10 I Waiting for event	I Update	I Queued Event	I 8987 I
11 I Waiting for event	I Update	I Queued Event	I 8136 I
12 I Waiting for event	I Update	I Queued Event	I 7931 I
13 I Waiting for event	I Update	I Queued Event	I 7523 I
14 I Active	I Simple Cmd.	I	I 7168 I
15 I Not active	I	I	I 6643 I
PF1 PF2 PF3	PF4 PF6-	PF7 PF8	PF12
Help Exit	Refresh		Menu

WORK Status

WORK status (option "W") displays the WORK area sizes (in blocks) for the

- data protection area (Work part 1; ADARUN LP parameter);
- area used for intermediate ISN lists (Work part 2; ADARUN LWKP2 parameter);
- area used for resulting ISN lists (Work part 3);

The equivalent direct command is

```
DISPLAY WORKSTATUS
16:57:32
            **** A D A B A S BASIC SERVICES *****
                                             2006-07-14
DBID 1955
                    - WORK Status -
                                             PACUW02
           W O R K Dataset
      +----+
      I Protection Area
                                       500 Blks I
      T-----T
      I Intermediate ISN Area
      I-----I
      I Resulting ISN Area
                                     1315 Blks I
      I Distributed Transaction Processing Area 500 Blks I
PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
            Exit
Help
                   DTP-area
                                            Menu
```

If you have DTP=RM in your ADARUN parameter settings, and press PF4 on the new screen, then the new screen DTP Work Area displays (shown below):

17:04:47	**** A	D A B A S BASIC SERVICES ***** - DTP Work Area -	2006-07-14 PACUK02
	Code	Service	
	D	Display PET-status users	
	H	Display heuristically terminated users	
	R	Display DTP rabns	
	U	Work Part 4 usage	
	X	Force heuristic BT/ET	

The DTP Work Area menu performs the following functions:

Function	Action
Display PET-status users	Displays the current environment of PET-status users. You can select one or more to display additional information.
Display heuristatically terminated users	Displays a list of the heuristatically terminated users. You can select one or more to display additional information.
Display DTP Rabns	Displays a list of allocated RABNs. You can select a user, display additional information, issue BT or ET, and display total RABNs for a user.
Work Part 4 Usage	Displays the breakdown of information of the Work Part 4.
Force Heuristic BT/ET	Issues a BT or ET for a selected user. Select the user through the "Display DTP RABNs" menu item.
PF2	Clears the selected user.

If you select Display PET-status users, the screen Display PET-Status Users displays (shown below):

```
17:17:39
               ***** A D A B A S BASIC SERVICES *****
                                                                2006-07-14
DBID 1955
                    - Display PET-Status Users -
                                                                PACUKD2
Mark entries with 'D' (Display):
M I Global ID
 I 000F710020640000B96353B18528B3820000000B96353B185286F02 I 044E0059 I
                                                            Ι
                                                                       Ι
_ I
_ I
                                                            Ι
                                                                       Ι
 Ι
                                                            Ι
_ I
                                                            Ι
                                                                       Ι
_ I
                                                            I
                                                                       Ι
 Ι
                                                            Ι
                                                                       Ι
                                                            Ι
                                                                       Ι
_ I
_ I
                                                            Ι
                                                                       Ι
```

```
PF1---- PF2----- PF3----- PF4----- PF6---- PF7---- PF8---- PF12----
Help Exit Refresh - + Menu
```

Cluster Usage



Note: This option is only active in an Adabas nucleus cluster environment.

Cluster usage (option "X") displays nucleus cluster statistics that are equivalent of those displayed using the DXCACHE, DXLOCK, and DXFILE operator commands. See the *Adabas Cluster Services* documentation or the *Adabas Parallel Services* documentation for more information.

The equivalent direct command is

<u>DI</u>SPLAY <u>CLU</u>STERSTATUS

```
17:20:31
                 **** A D A B A S BASIC SERVICES *****
                                                                 2006-07-14
                            - Cluster Usage -
                                                                 PACUX02
                      Code
                              Service
                       C
                              Cache statistics
                       F
                              File statistics
                              Lock statistics
                       L
                              Help
                              Exit
         Code ....._
         File Number .. 0
         Database ID .. 1955
                                                  NucID .. 1021
                             (WIS1955)
Command ==>
```

PF1 PF2	PF3	PF4	PF6	PF9	PF10	PF12
Help	Exit			Fuse	Flist	Menu

Cache Statistics

Choosing Cache Statistics (option "C") from the Cluster Usage menu displays the following menu:

```
**** A D A B A S BASIC SERVICES ****
17:24:23
                                                    2006-07-14
                     - Cache Statistics -
                                                    PACUX12
             Code Service
                   _____
                  Cast-out / Directory
               K
               P Publishing requests
               Χ
                  Individual cache blocks
                  Exit
               ? Help
              ____
   Code .....
   Database ID .. 1955 (WIS1955) NucID .. 1021
PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
            Exit Refresh
```

Cast-out / Directory

Choosing Cast-out / Directory (option "K") from the Cache Statistics menu display the following:

```
17:31:23 ***** A D A B A S BASIC SERVICES ***** 2006-07-14
DBID 1955
                    - Cast-out / Directory -
                                                    PACUX12
NucID 1021
      Cast-out Directory Reads
                               Directory Reads
      -----
      Total ..... 28
Sync .... 1
Async .... 27
                               Total .....
                                 Sync ....
                                 Async ....
      Unlock Cast-out Calls
      Total .....
        Sync ....
                       1
        Async .... 27
```

```
PF1---- PF2---- PF3---- PF4---- PF7---- PF8---- PF9----- PF12----
Help Exit Refresh Detail Menu
```

Counters have a multiplier column with the following values:

Value	The total shown is in
blank	bytes
K	kilobytes
M	megabytes
G	gigabytes
T	terabytes

If a number has a multiplier shown, it has been divided by the multiplier, showing the significant digits to 9 places with no decimal point.

Press PF9 to see the entire value. This value is the exact count up to 20 digits in length.

Publishing Requests

Choosing Publishing Requests (option "P") from the Cache Statistics menu display the following:

17:36:21 DBID 600 NucID 2	***** A D A B A S BASIC - Publishing Req		2006-07-14 PACUX12
	Publishing Request Cat		
	Update sync	0	
	BT or CL or ET	0	
	Redo threshold	12	
	Full bufferpool	10	
	All blocks	2	
	Specific RABN	8	
	File DS blocks	4	
	All DSST blocks	0	
	File NI blocks	8	
DE1 DE0	DE2 DE4 DE7	DE0 DE0	DE10
	PF3 PF4 PF7		
Help	Exit Refresh	Detail	Menu

All Cache Blocks

Choosing All Cache Blocks (option "X") from the Cache Statistics menu display the following:

17:43:05 ***** A DBID 1955 NucID 1021 Reads	D A B A S BA - All Cache	SIC SERVICES ***** Blocks - Writes	2006-07-14 PACUX12
Total	167 24 143	Total	38,176 15,148
In cache Not in cache Struc. full Cast-out Reads	49 118 0	Written Not written Struc. full Other	38,176 0 0
Total Sync Async	212 212 0	Validates Invalid Deletes Timeouts Redo processes	
PF1 PF2 PF3 Help Repos Exit			

Use PF7 and PF8 to scroll through the cache blocks; use PF2 to reposition.

Statistics are displayed for the following:

- All cache blocks;
- Address converter (AC) cache blocks;
- Data Storage (DS) cache blocks;
- Data Storage space table (DSST) cache blocks;
- File control block (FCB) cache blocks;
- Normal index (NI) cache blocks;
- Upper index (UI) cache blocks.

Press PF9 from the above screen to display the following detail screen:

17:47:09 DBID 1955 NucID 1021	***** A D A B A S BASIC SERVICES ***** 2006-07-14 - All Cache Blocks - PACUX12		
Reads		Writes	
Total		Total	38,176
Sync	24	Sync	15,148
Async	143	Async	23,028
In cache	49	Written	38,176
Not in	118	Not writ	0
Stru.full.	0	Stru.full .	0
Cast-out Reads		Other	
Total		Validates	187,677
Sync	212	Invalid	43
Async	0	Deletes	0
		Timeouts	0
		Redo procs	0
	I	Press Enter to continu	e

File Statistics

Choosing File Statistics (option "F") from the Cluster Usage menu for file 25 displays the following menu:

17:52:02 ***** DBID 1955 NucID 1021		BASIC SERVICES ***** tatistics -	2006-07-14 PACUX22
Reads		Writes	
Total	67	Total	20,157
Sync	0	Sync	7,583
Async	67	Async	12,574
In cache	0	Written	20,157
Not in cache	67	Not written	0
Struc. full	0	Struc. full	0
Cast-out Reads		Other	
Total	78	Validates	79,248
Sync	78	Invalid	0
Async	0	Deletes	0
		Timeouts	0

				Redo	processes	5	0
PF1	PF2	PF3	PF4	PF7	PF8	PF9	PF12
Help	Repos	Exit	Refresh			Detail	Menu

Lock Statistics

Choosing Lock Statistics (option "L") from the Cluster Usage menu displays the following menu:

17:58:	16 **** A D	A B A S BASIC - Lock Statist		2006-07-14 PACUX32
Code	Service	Code	Service	
A B C D E F G H I	Buffer flush lock Cancel lock Checkpoint lock DSF lock ETID lock File-lock-table lock FST lock GCB lock Global ET sync lock Exit	J K L M N O P Q R S	Global update command Hold ISN lock New-Data-RABN lock Online save lock Parameter lock Recovery lock RLOG lock Security lock Spats lock Unique descriptor lock	
? PF1 Help	Help	PF4 PF6	NucID 1021	PF12 Menu

Each of the options on the Lock Statistics menu displays statistics for a particular lock. For each lock, the screen displays obtain and release information about the various types of that lock that are currently in use by a cluster nucleus:

- The system may obtain locks conditionally or unconditionally, synchronously or asynchronously. A conditional request for a lock may be granted or rejected.
- Releases may be issued synchronously or asynchronously.


Hold ISN Lock

Choosing Hold ISN Lock (option "J") from the Lock Statistics menu displays the following:

18:08	3:16		**** A I	DABAS	BASIC	SERVICES ***	* *	2006-07-14
DBID	195	55		- Hold 1	SN Loc	k -		PACUX32
NucII	0 102	21						
	Obta	ains]	Releases		
	Cond	ditional .		16,017		Issued		16,017
	C	Franted .		16,017		Sync	•	15,971
	F	Rejected .		0		Async	•	46
	Unco	onditional	l	0				
	Sync	2		158				
	Asyr	nc		15,859				
PF1		PF2	PF3	- PF4	PF6	PF7	PF8	PF12
Help		Repos	Exit	Refresh		PrevLok	NxtLok	Menu

Use PF7 and PF8 to scroll through the locks; use PF2 to reposition. $\,$

11 Replicator Management



12 Display Maintenance Levels



Note: This function is only available for Adabas version 8 or above databases.

Selecting Display Maintenance Levels (option "Z") from the Session Monitoring menu displays information about the Adabas nucleus modules:

```
18:13:09
               **** A D A B A S
                                    BASIC SERVICES *****
                                                                2006-07-14
  DBID 105
                        - Display Maintenance Levels -
                                                                   DPACZ02
  Select Module Name:
    ADARUN RUNMVS Date 2006-07-14, Version 8.1. 0, Zap Base AO10000
           RUNIND Date 2006-07-14, Version 8.1. 0, Zap Base AI10000
                    Date 2006-07-14, SM Level 00, Zap Level 0000
    ADATSP
                      Zaps 0034 0040 0043 0083 0084 0099
                      Date 2006-07-14, SM Level 00, Zap Level 0000
    ADATCP
                      Zaps 0136
                      Date 2006-07-14, SM Level 00, Zap Level 0000
    ADAMSG
                      Date 2006-07-14, SM Level 00, Zap Level 0000
    ADAIOR
                      Date 2006-07-14, SM Level 00, Zap Level 0000
    ADAIOS
                      Zaps 0001 0003 0004 0005 0007
                      Date 2006-07-14, SM Level 00, Zap Level 0000
    ADANC0
                      Zaps 0036
 Command ===>
 PF1---- PF2---- PF3---- PF4---- PF6---- PF7---- PF8---- PF12----
 Help
                    Exit
                                                                  Menu
```

Maintenance levels for each module are displayed. Any ZAPs that are applied to the module are also listed.

The list of modules can be limited by entering a specific module name in the Select Module Name field at the top of the screen. A starting value may also be used. For example, specifying ADANC3

displays information for the ADANC3 module only. Specifying ADANC* lists all modules with names that begin with ADANC.

Index

Α	N
ADARUN	II.
parameters	Nucleus file
using Basic Services, 11	display status using Basic Services, 37
C	
	Р
Cluster	•
display usage statistics	Protection log
using Basic Services, 43	display status
Command Queue	using Basic Services, 38
display	
using Basic Services, 20	Q
Commands	u
display overall usage	Queues
using Basic Services, 34	display
display usage per user	using Basic Services, 17
using Basic Services, 28	
	R
D	IX.
_	Replicator
Display	Management
installed products	using Adabas Basic Services, 51
using Basic Services, 15	Resources
	monitor/display overall usage
F	using Basic Services, 33
	produce/display current statistics
Files	using Basic Services, 25
display	
overall usage", "using Basic Services, 35	S
usage per user, using Basic Services, 29	J
	Session
H	display status
**	using Basic Services, 38
High water marks	Session monitoring
display current for selected pools and queues	in a multiprocessing environment, 1
using Basic Services, 36	using Basic Services,
Hold Queue	overview, 2
display	Statistics
using Basic Services, 21	create/display
	using Basic Services, 26, 28
M	using Basic Services for Adabas versions prior to 6.2, 27
IVI	System
Maintenance	display status
display levels	using Basic Services, 38
using Adabas Basic Services, 53	
Multiprocessing	
1 U	

monitoring sessions, 1

T

```
TCP/IP
   maintain URLs online, 31
Threads
   display usage statistics
      using Basic Services, 40
U
User
   display command usage
      using Basic Services, 28
   display file usage
      using Basic Services, 29
   display resource usage
      using Basic Services, 26
User profiles
   maintain using Adabas Basic Services, 5
User Queue Element
   display
       using Basic Services, 19
W
Work
   display pool usage statistics
      using Basic Services, 36
```

display status of areas using Basic Services, 41