

ADADBS Error Messages

Overview of Messages

| | | | | | |
|-----------|-----------|-----------|-----------|-----------|-----------|
| ERROR-114 | ERROR-121 | ERROR-122 | ERROR-123 | ERROR-124 | ERROR-125 |
| ERROR-126 | ERROR-127 | ERROR-128 | ERROR-129 | ERROR-130 | ERROR-131 |
| ERROR-132 | ERROR-133 | ERROR-134 | ERROR-135 | ERROR-137 | ERROR-138 |
| ERROR-139 | ERROR-140 | ERROR-141 | ERROR-143 | ERROR-144 | ERROR-145 |
| ERROR-146 | ERROR-147 | ERROR-148 | ERROR-149 | ERROR-150 | ERROR-151 |
| ERROR-152 | ERROR-153 | ERROR-154 | ERROR-155 | ERROR-156 | ERROR-157 |
| ERROR-158 | ERROR-159 | ERROR-160 | ERROR-161 | ERROR-162 | ERROR-163 |
| ERROR-164 | ERROR-165 | ERROR-166 | ERROR-167 | ERROR-168 | ERROR-169 |
| ERROR-170 | ERROR-172 | ERROR-173 | ERROR-174 | ERROR-175 | ERROR-176 |
| ERROR-178 | ERROR-179 | ERROR-182 | ERROR-183 | ERROR-184 | ERROR-186 |
| ERROR-187 | ERROR-188 | ERROR-189 | ERROR-190 | ERROR-191 | ERROR-194 |

ERROR-114 Invalid value for parameter ASSOPFAC or DATAPFAC

Explanation The value for a padding factor must be in the range 1 to 90%.

Action Correct the parameter value and rerun the job.

ERROR-121 Invalid encoding value (1-4095)

Explanation A valid encoding value is in the range 1 through 4095.

Action Supply a valid encoding value for the parameter and rerun the job.

ERROR-122 Invalid file number specification

Explanation Depending on the function to be performed, one or more file numbers must be supplied.

Action Supply the correct parameter value and rerun the job. Refer to the Adabas Utilities documentation for more information.

ERROR-123 Invalid value for the parameter MODE

Explanation Either ON or OFF is required to specify the new mode for DS or ISN reusage.

Action Supply the correct parameter value and rerun the job.

ERROR-124 Invalid value for the parameter PRTY

Explanation A valid value is in the range 1 through 255.

ERROR-125 Invalid value for the parameter ASSOSIZE/DATASIZE

Explanation One of the parameters ASSOSIZE or DATASIZE is mandatory. You cannot use both.

Action Supply the correct parameter value and rerun the job.

ERROR-126 Invalid value for a SIZE parameter

Explanation Either the xxSIZE parameter specified an incorrect value, or more than one xxSIZE parameter was specified.

Action Supply the correct parameter value and rerun the job. Only one SIZE parameter can be specified. The value must be specified in blocks. Choose one of the following sizes:

- ACSIZE
- DSSIZE
- NISIZE
- UISIZE

ERROR-127 Invalid value for the parameter LENGTH, OPTION, or FORMAT

Explanation The following rules apply:

- Only one of the LENGTH, OPTION, or FORMAT parameters can be specified.
- If specified, the value of the LENGTH parameter must be greater than zero and less than or equal to the permitted maximum according to the requested field's format.
- If specified, the only OPTION parameter value permitted is LA.

Action Supply the correct parameter value and rerun the job.

ERROR-128 Invalid value for the parameter TODATE

Explanation The parameter TODATE must be specified in the format:

TODATE=YYYYMMDD

Action Supply the correct parameter value and rerun the job.

ERROR-129 Mandatory parameter user ID missing

Explanation The priority is assigned to a specific user which is uniquely identified by its user ID. The user ID parameter is missing.

Action Supply the correct parameter value and rerun the job.

ERROR-130 Invalid value for the parameter descriptor

Explanation The value is one of the following:

- missing;
- not found in the FDT; or
- found in the FDT, but is not a descriptor.

Action Supply the correct parameter value and rerun the job.

ERROR-131 Invalid value for the parameter name

Explanation A valid value for the NAME parameter is required.

Action Supply the correct parameter value and rerun the job.

ERROR-132 Jobname or IDENT parameter missing

Explanation Specify at least one of these parameters. Data integrity may be lost if the whole DIB block is reset. The DDIB operator command may be used to obtain information about the current contents of the DIB.

Action Supply the correct parameter value and rerun the job.

ERROR-133 Invalid or missing field name

Explanation One of the following conditions exists:

- Field name is missing;
- Field name not found in FDT;
- Field is a group, subdescriptor.....;
- Field has FI option.

Action Supply the correct parameter value and rerun the job.

| | |
|--------------------|--|
| ERROR-134 | Invalid value for the parameter <i>parameter</i> |
| Explanation | The only valid values for the parameter listed in the message are YES or NO. |
| Action | Supply the correct parameter value and rerun the job. |
| ERROR-135 | Missing parameter for OPERCOM function |
| Explanation | At least one valid operator command must be supplied. |
| Action | Supply a valid operator command and rerun the job. |
| ERROR-137 | Size must be specified in cylinders |
| Explanation | ASSOSIZE and/or DATASIZE cannot be specified in blocks. |
| Action | Supply the correct parameter value in number of cylinders and rerun the job. |
| ERROR-138 | Size must be specified in blocks |
| Explanation | ASSOSIZE and/or DATASIZE cannot be specified in cylinders. |
| Action | Supply the correct parameter value in number of blocks and rerun the job. |
| ERROR-139 | Invalid dataset number |
| Explanation | See the Adabas Utilities documentation for a description of data set numbers. |
| Action | Supply the correct parameter value, and rerun the job. |
| ERROR-140 | Invalid value for MAXDS, MAXNI or MAXUI |
| Explanation | The values for these parameters must be specified in blocks and must not be larger than 65,535. |
| Action | Supply a correct parameter value and rerun the job. |
| ERROR-141 | Missing function parameter |
| Explanation | The specific ADADBS function was not specified in the ADADBS job. |
| Action | Specify the appropriate function parameter as described in the Adabas Utilities documentation, and rerun the ADADBS job. |

ERROR-143 Invalid value for PGMREFRESH

Explanation Only "yes" or "no" are allowed as parameter values.

Action Supply the correct parameter value and rerun the job.

ERROR-144 Invalid value for parameter REVIEW

Explanation The values NO, LOCAL or hub are allowed.

Action Supply the correct parameter value and rerun the job.

ERROR-145 Invalid Adabas state for "TRAN SUSPEND/RESUME"

Explanation An online database or file save is executing, or Adabas is still processing the last TRAN SUSPEND and TRAN RESUME function.

ERROR-146 TRESUME timer expired before resume occurred

Explanation You ran the TRAN RESUME job, but the timer set by TRESUME (defaults to 120 seconds unless set in the JCL) had already expired. Once the timer expires, Adabas immediately begins to return to "normal status".

ERROR-147 "TRAN SUSPEND" already in progress

Explanation A TRAN SUSPEND is running. Either the timer must expire or a TRAN RESUME job must be successfully executed before another TRAN SUSPEND job can be started.

ERROR-148 No previous "TRAN SUSPEND" to resume

Explanation No TRAN SUSPEND job has been started.

ERROR-149 Invalid when Adabas is "MODE=SINGLE"

Explanation Adabas is running in single-user mode. MODE=MULTI is required.

ERROR-150 ET-SYNC failed

Explanation The ET-SYNC was not successful; the database cannot be quiesced.

Action Contact your Software AG technical support representative.

ERROR-151 TARGET is invalid.

Explanation Replication with TARGET = DBID, NUCID, 0, or greater than 65535 is not allowed.

Action Supply the correct parameter value and rerun the job.

ERROR-152 Parameters NOKEY and KEY are mutually exclusive.

Explanation Specifying both NOKEY and KEY is not allowed.

Action Supply the correct parameter value and rerun the job.

ERROR-153 Conflicting parameter for replication OFF.

Explanation Additional parameters are not allowed.

Action Supply the correct parameter value and rerun the job.

ERROR-154 Invalid KEY for replication. The specified KEY field <field> is not defined as a descriptor on the file to be replicated.

Explanation A replication key field must be defined as a descriptor.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-155 Invalid KEY for replication. The specified KEY field <field> does not exist on the file to be replicated.

Explanation The specified replication key field must exist.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-156 Invalid replication request.

Explanation REPLICATION ON was attempted for a file that is already replicated.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-157 Invalid replication request.

Explanation A REPLICATION MODIFY or REPLICATION OFF was attempted for a file that is not currently replicated.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-158 Invalid FILE for replication.

Explanation A replicated file must exist on the database and may not be an Adabas system file or ciphered.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-159 Invalid replication request.

Explanation REPLICATION ACTIVATE was attempted for a file that already has replication activated.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-160 Parameters ACTIVATE and DEACTIVATE are mutually exclusive.

Explanation Specifying both ACTIVATE and DEACTIVATE is not allowed.

Action Supply the correct parameter value and rerun the job.

ERROR-161 Invalid value for parameter DSBI.

Explanation The only valid values for DSBI are "ON" or "OFF".

Action Supply the correct parameter value and rerun the job.

ERROR-162 Conflicting parameter for replication ON.

Explanation ACTIVATE / DEACTIVATE may not be specified.

Action Supply the correct parameter value and rerun the job.

ERROR-163 Event Replicator Server function only allowed for Event Replicator database

Explanation The ADADBS Event Replicator Server function is only valid for an Event Replicator database.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-164 The specified destination *destination* was not found.

Explanation The destination listed in the message is not defined to the Event Replicator Server.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-165 **The specified subscription *subscription* was not found.****Explanation** The subscription listed in the message is not defined to the Event Replicator Server.**Action** Investigate the cause of the error. Correct it and rerun the job.**ERROR-166** **The specified DBID was not found.****Explanation** The specified DBID is not defined to the Event Replicator Server.**Action** Investigate the cause of the error. Correct it and rerun the job.**ERROR-167** **The specified FILE/DBID was not found.****Explanation** The specified file for the specified DBID is not defined to the Event Replicator Server.**Action** Investigate the cause of the error. Correct it and rerun the job.**ERROR-168** **The specified destination *destination* was already *active/inactive*.****Explanation** The Event Replicator Server detected the destination listed in the message was already active or inactive.**Action** Investigate the cause of the error. Correct it and rerun the job.**ERROR-169** **The specified FILE/DBID was already *active/inactive*.****Explanation** The Event Replicator Server detected the specified file for the specified DBID was already active or inactive.**Action** Investigate the cause of the error. Correct it and rerun the job.**ERROR-170** **The specified subscription *subscription* was already *active/inactive*.****Explanation** The Event Replicator Server detected the subscription listed in the message was already active or inactive.**Action** Investigate the cause of the error. Correct it and rerun the job.**ERROR-172** **Invalid value for DBID.****Explanation** DBIDs greater than 65535 are not allowed.**Action** Supply the correct parameter value and rerun the job.

ERROR-173 {CLOSE | OPEN} failed for specified destination *destination-name*

Explanation ADADBS detected that the Event Replicator Server could not CLOSE or OPEN the destination listed in the message.

Action Investigate the cause of the error. The Event Replicator Server job log will provide more details on why the request failed.

ERROR-174 The specified input queue *queue-name* was not found.

Explanation The input queue (IQUEUE) listed in the message is not defined to the Event Replicator Server.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-175 {CLOSE | OPEN} failed for specified input queue *queue-name*

Explanation ADADBS detected that the Event Replicator Server could not CLOSE or OPEN the input queue (IQUEUE) listed in the message.

Action Investigate the cause of the error. The Event Replicator Server job log will provide more details on why the request failed.

ERROR-176 Missing parameter: DESTINATION or IQUEUE required

Explanation Either DESTINATION or IQUEUE must be specified for the OPEN and CLOSE functions.

Action Investigate the cause of the error. Correct it and rerun the job.

**ERROR-178 The specified destination *dest-name* may not be active
Data still exists on the SLOG system file for this inactive destination**

Explanation An attempt was made to activate the destination named in the message (*dest-name*) while transactions for the destination still exist on the SLOG system file from the last time it was activated.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-179 **The specified DBID/file may not be activated**
The SLOG has been suspended for database-related input transactions and one or more transactions exist on the SLOG system file for this inactive DBID/file

Explanation An attempt was made to activate a DBID/file combination that was deactivated because the SLOG system file was full.

Action Investigate the cause of the error. Correct it and rerun the job.

ERROR-182 **No file number given**

Explanation The mandatory operand, FILE, was not specified with the MUPEX or RECORDSPANNING function.

Action Supply the correct parameter value and rerun the job. For more information, read about the MUPEX and RECORDSPANNING functions of the ADADBS utility in your Adabas utilities documentation.

ERROR-183 **Invalid MUPECOUNT option (1/2)**

Explanation A value other than "1" or "2" was specified for the MUPECOUNT parameter in an ADADBS MUPEX function run. The only valid values for MUPECOUNT are "1" or "2".

Action Supply the correct parameter value and rerun the job. For more information, read about the MUPEX function of the ADADBS utility in your Adabas utilities documentation.

ERROR-184 **MUPECOUNT specification is invalid. The file contains a PE and has records.**

Explanation To set the MUPECOUNT parameter to "1", the file must either be empty or have no PE fields. To set the MUPECOUNT to "2", the file cannot contain a PE field that is part of a DE field unless the file is empty.

Action Supply the correct parameter value or release the descriptors and rerun the job. For more information, read about the MUPEX function of the ADADBS utility in your Adabas utilities documentation.

ERROR-186 Conflicting file options

Explanation One of the following circumstances occurred:

- The file specified is a system file.
- The file specified is a coupled file.
- The file specified is an ADAM file.
- The file specified is a replicated file.
- Only privileged commands are permitted against this file.
- The file specified is in load status.
- MIXDSDEV is not permitted for spanned data storage files.

Action Correct the file or parameters and rerun the ADADBS job.

ERROR-187 TIMELIMIT exceeded

Explanation The RECORDSPANNING or SPANCOUNT functions's time limit (set by the TIMELIMIT parameter) was exceeded.

Action Change the TIMELIMIT parameter value and rerun the job. For more information, read about the RECORDSPANNING and SPANCOUNT functions of the ADADBS utility in your Adabas utilities documentation.

ERROR-188 Invalid RECORDSPANNING request

Explanation The MODE=OFF parameter of the RECORDSPANNING function cannot be specified for a file that already contains spanned data storage records.

Action Ensure that the specified file contains no spanned data storage records and then rerun the ADADBS job. For more information, read about the RECORDSPANNING function of the ADADBS utility in your Adabas utilities documentation.

ERROR-189 An I/O error occurred

Explanation An I/O error occurred executing the specified function

Action Research and correct the cause of the error and rerun the ADADBS job.

ERROR-190 File specified is not spanned

Explanation The file specified does not have spanned data storage records enabled.

Action Specify a file with spanned data storage records enabled and rerun the ADADBS job.

ERROR-191 Replication may not be turned on for a file with spanned data storage records.

Explanation Replication may not be turned on for a file with spanned Data Storage records.

Action Review and correct the parameters specified in the ADADBS run and ensure that you are not trying to replicate a file containing spanned records. Then try running the job again.

ERROR-194 Replication not active for Adabas

Explanation Input information to ADADBS is requiring that the Adabas database have REPLICATION=YES (replication must be active) specified in the parameters to accomplish the request. However, replication for the database is not active.

Action Examine the input to ADADBS for correctness. You may have to modify, stop, and restart the Adabas database to allow replication to be active.