

Nucleus Startup Error Messages

This section describes error messages and response codes issued by the Adabas nucleus. These errors may occur during nucleus startup, usually as the result of an ADARUN parameter error. The nucleus prints an error message and then terminates with an abnormal end (abend) code of 20 (see the abend code descriptions).

Refer to the Adabas Operations documentation for a description of the ADARUN parameters.

These error messages have the following format:

```
PARM-ERROR nnn [detected during system open]
```

-where "nnn" is one of the startup errors and has the corresponding meaning described here. The error message may be followed by a brief error description.

Overview of Messages

| | | | |
|----------------|----------------|----------------|----------------|
| PARM ERROR 1 | PARM ERROR 2 | PARM ERROR 3 | PARM ERROR 4 |
| PARM ERROR 5 | PARM ERROR 6 | PARM ERROR 7 | PARM ERROR 8 |
| PARM ERROR 9 | PARM ERROR 10 | PARM ERROR 11 | PARM ERROR 12 |
| PARM ERROR 13 | PARM ERROR 14 | PARM ERROR 15 | PARM ERROR 16 |
| PARM ERROR 17 | PARM ERROR 18 | PARM ERROR 19 | PARM ERROR 20 |
| PARM ERROR 21 | PARM ERROR 22 | PARM ERROR 23 | PARM ERROR 24 |
| PARM ERROR 25 | PARM ERROR 26 | PARM ERROR 27 | PARM ERROR 28 |
| PARM ERROR 29 | PARM ERROR 30 | PARM ERROR 31 | PARM ERROR 32 |
| PARM ERROR 33 | PARM ERROR 34 | PARM ERROR 35 | PARM ERROR 36 |
| PARM ERROR 37 | PARM ERROR 38 | PARM ERROR 39 | PARM ERROR 40 |
| PARM ERROR 41 | PARM ERROR 42 | PARM ERROR 43 | PARM ERROR 44 |
| PARM ERROR 45 | PARM ERROR 46 | PARM ERROR 47 | PARM ERROR 48 |
| PARM ERROR 49 | PARM ERROR 50 | PARM ERROR 51 | PARM ERROR 52 |
| PARM ERROR 53 | PARM ERROR 54 | PARM ERROR 55 | PARM ERROR 56 |
| PARM ERROR 57 | PARM ERROR 58 | PARM ERROR 59 | PARM ERROR 60 |
| PARM ERROR 61 | PARM ERROR 62 | PARM ERROR 63 | PARM ERROR 64 |
| PARM ERROR 65 | PARM ERROR 66 | PARM ERROR 67 | PARM ERROR 68 |
| PARM ERROR 69 | PARM ERROR 70 | PARM ERROR 71 | PARM ERROR 72 |
| PARM ERROR 73 | PARM ERROR 74 | PARM ERROR 75 | PARM ERROR 76 |
| PARM ERROR 77 | PARM ERROR 78 | PARM ERROR 79 | PARM ERROR 80 |
| PARM ERROR 81 | PARM ERROR 82 | PARM ERROR 83 | PARM ERROR 84 |
| PARM ERROR 85 | PARM ERROR 86 | PARM ERROR 87 | PARM ERROR 88 |
| PARM ERROR 90 | PARM ERROR 91 | PARM ERROR 92 | PARM ERROR 93 |
| PARM ERROR 94 | PARM ERROR 95 | PARM ERROR 96 | PARM ERROR 97 |
| PARM ERROR 98 | PARM ERROR 99 | PARM ERROR 100 | PARM ERROR 101 |
| PARM ERROR 102 | PARM ERROR 103 | PARM ERROR 104 | PARM ERROR 105 |
| PARM ERROR 106 | PARM ERROR 109 | PARM ERROR 110 | PARM ERROR 111 |

PARM ERROR 1

Explanation The Associator data set(s) could not be opened or an error occurred during processing of the GCBs:

- invalid or incorrect DEVICE parameter;
- missing or invalid JCL or data sets for ASSO;
- mismatching database ID; or
- missing checkpoint file.

This error may result from a data set not located on a cylinder boundary.

Action For single-user mode, the appropriate Adabas job control statements must be specified.

PARM ERROR 2

Explanation Data Storage data set(s) could not be opened. This probably indicates missing or invalid JCL or data sets for DATA.

Action For single-user mode, the appropriate Adabas job control statements must be specified.

PARM ERROR 3

Explanation The Work data set could not be opened, or the last Work block was not readable. This probably indicates invalid DD/WORKR1 JCL or data set, or a data set not located on a cylinder boundary.

Action For single-user mode, the appropriate Adabas job control statements must be specified.

PARM ERROR 4

Explanation The value of the ADARUN statement's number of threads (NT) parameter is invalid. The allowed range is from 4 to 250.

PARM ERROR 5

Explanation The value of the ADARUN statement's number of hold queue elements (NH) parameter is invalid. The allowed range is from 20 to 16,777,215.

PARM ERROR 6

Explanation The value of the ADARUN statement's user queue element count (NU) parameter is invalid. The allowed range is from 20 to 16,777,215.

PARM ERROR 7

Explanation The value of the ADARUN statement's user ISN hold queue count (NISNHQ) is invalid. The allowed maximum is the smaller of 1/4 the NH parameter value and 65,535.

PARM ERROR 8

Explanation The value of the ADARUN statement's command queue element count (NC) parameter is invalid. The allowed range is from 20 to 32,767.

PARM ERROR 9

Explanation The value of the ADARUN statement's Adabas cluster nucleus ID (NUCID) is invalid. The maximum value is 65000.

PARM ERROR 10

Explanation The value of the ADARUN statement's ISN list table length (LI) parameter is invalid. The minimum value is 2000.

PARM ERROR 11

Explanation The value of the ADARUN statement's sequential command table (LQ) parameter is invalid. The minimum value is 2000.

PARM ERROR 12

Explanation The value of the ADARUN statement's buffer pool length (LBP) parameter is invalid. The minimum value is 80,000.

PARM ERROR 13

Explanation The value of the ADARUN statement's internal format pool (LFP) parameter is invalid. the minimum value is 6000.

PARM ERROR 14

Explanation The value of the ADARUN statement's work pool length (LWP) parameter is invalid. The minimum value is 80,000.

PARM ERROR 15

Explanation The value of the ADARUN statement's sort area length size (LS) parameter is invalid. The allowed range is from 19,968 to (LWP/2) -19,968.

PARM ERROR 16

Explanation The value of the ADARUN statement's security pool length (LCP) parameter is invalid. The allowed range is from 2000 to 16,777,215.

PARM ERROR 17

Explanation If you have Adabas Transaction Manager version 7.4 or earlier installed, the size of Work part 1 (the value of the ADARUN statement's LP parameter) is less than 200 blocks or greater than the Work data set size minus the space required for Work part 2 (the LWKP2 parameter), Work part 3 (minimum of 50 blocks), and, if used, Work part 4 (the LDTP parameter).

If you have Adabas Transaction Manager version 7.5 or later installed, the size of Work part 1 (the value of the ADARUN statement's LP parameter) is less than 200 blocks or greater than the Work data set size minus the space required for Work part 2 (the LWKP2 parameter), and Work part 3 (minimum of 50 blocks).

PARM ERROR 18

Explanation Fewer than 50 blocks are available for Work part 3. Autorestart has been executed.

PARM ERROR 19

Explanation The DBID of the general control blocks (GCBs) and DBID stored on the Work data set do not match. The Work data set contains autorestart information for a different database (DBID).

PARM ERROR 20

Explanation GETMAIN below the 16MB line failed.

PARM ERROR 21

Explanation The general control blocks (GCBs) contain an invalid device type. The GCBs may have been overwritten, damaged, or otherwise destroyed.

PARM ERROR 22

Explanation An I/O error occurred when writing ASSO. The region is too small. The RABN that was to be written is printed.

PARM ERROR 23

Explanation A nucleus entry already exists in the data integrity block (DIB) for one of the following reasons:

- An attempt was made to start a nucleus while another update nucleus was still active; or
- The previous nucleus session terminated abnormally but the "nucleus" DIB entry was not removed.

Action If a DIB entry remained after an abnormal termination, rerun the job with the ADARUN IGNDIB=YES parameter. If the FORCE=YES parameter had been applied, then the nucleus must be started with FORCE=YES and IGNDIB=YES. Here the DIB entry will only be removed once the ID Table initialization had been successful. Running with IGNDIB=YES alone will result in a PARM ERROR 26.

PARM ERROR 24

Explanation An I/O error occurred when reading ASSO. The RABN that was to be read is printed.

PARM ERROR 25

Explanation The Adabas nucleus cannot be started because a conflicting utility DIB entry was found. Either a utility with exclusive database control or an ADASAV (SAVE FILE or SAVE database) job is running.

Action If an ADASAV SAVE FILE or ADASAV SAVE (database) ended abnormally, the nucleus can be restarted with the ADARUN IGNDIB=YES parameter; however, the save tape cannot be used for future RESTORE operations.

PARM ERROR 26

Explanation Interregion communication could not be established.

Action This message should be preceded by message ADAM98. If the ADAM98 error reason is “DUPLICATE ID (LOCAL)” and a previous nucleus ended such that it was not able to clean up, you may wish to restart specifying FORCE=YES. Refer to ADAM98 message documentation for information about other possible errors.

If IGNDIB=YES was specified, then the nucleus must be started with FORCE=YES and IGNDIB=YES. Here the DIB entry will only be removed once the ID Table initialization had been successful. Running with FORCE=YES alone will result in a PARM ERROR 23.

Note:

Specifying FORCE=YES with the DBID of a currently active nucleus can disrupt operations on that nucleus. In addition, users of the old database whose ID is overwritten by the FORCE=YES option lose access to the database. Therefore, FORCE=YES should only be specified if absolutely necessary. For more information, refer to the FORCE parameter description in the Adabas Operations documentation.

PARM ERROR 27

Explanation The ADARUN statement’s PLOGRQ parameter is specified as or defaults to YES, FORCE, or SEL, but a protection log and related parameters have not been provided.

PARM ERROR 28

Explanation The protection log (PLOG) data set(s) could not be opened, or the last dual or multiple PLOG block was not readable. This is probably due to incorrect PLOG data set definition, specification, or job control statements.

PARM ERROR 29

Explanation Invalid command log (CLOG) device definition.

PARM ERROR 30

Explanation FREEMAIN error.

PARM ERROR 31

Explanation System autorestart error (see the nucleus response code).

PARM ERROR 32

Explanation Error during buffer flush.

PARM ERROR 33

Explanation Error during Work initialization.

PARM ERROR 34

Explanation The nucleus is not allowed to start with READONLY=YES when an autorestart is pending.

PARM ERROR 35

Explanation File control block (FCB) check failed. The FCB may have been overwritten or otherwise destroyed.

PARM ERROR 36

Explanation Timer initialization failed, or operator communication could not be established.

PARM ERROR 37

Explanation GETMAIN in common storage (CSA) failed; interregion communication could not be established. The specific reason is given in a detailed ADAM nn message.

PARM ERROR 38

Explanation DIB overflow.

PARM ERROR 39

Explanation Work pool is too small for the number of threads.

Action Increase the LWP parameter value to at least 25 kilobytes times the number of threads.

PARM ERROR 40

Explanation Database version mismatch: the database is not version *version revision-level*.

Action Run the ADACNV utility to bring the database to the correct version.

PARM ERROR 41

Explanation Parallel participant table (PPT) initialization error:

- an I/O error occurred reading or writing a PPT block (RABN); or
- a PPT length error occurred when a bad PPT block was encountered.

| | |
|----|--|
| 1 | An error occurred reading the PPT block (RABN) to determine the PLOG entries from the last database session. |
| 2 | An error occurred trying to obtain the constant set for the PPT. |
| 3 | An error occurred in the PPT verification routine. |
| 4 | The PPT area is full; that is, there are already 32 active PPT entries. |
| 5 | An error occurred attempting to check for any active PPT blocks. |
| 6 | An error occurred while reading the PPT block prior to updating it. |
| 7 | A bad file name was detected in the PPT for the Work data set. |
| 8 | An error occurred trying to obtain the constant set for the PPT in order to log the Work data set in the PPT for the first time (no previous entry was found in the PPT for the Work data set). |
| 9 | A bad file name was detected in the PPT for the Work data set when logging the PPT entry for the first time (no previous entry was found for the Work data set). |
| 10 | An error occurred trying to obtain the constant set for the PPT entry in order to override a previous PPT entry. |
| 11 | A bad file name was found when attempting to log the PLOGR1 data set in the PPT. |
| 12 | A bad file length was found when attempting to compare the new PLOGR1 data set against the old one. |
| 13 | A bad file name was found when attempting to log the PLOGR2 data set in the PPT. |
| 14 | A bad file length was found when attempting to compare the new PLOGR2 data set against the old one. |
| 15 | An error occurred trying to obtain the constant set for the PPT prior to updating the PPT. Either a different PLOG data set was detected or no PLOGs are being used. |
| 16 | An error occurred when trying to obtain the constant set for the PPT prior to writing the PPT. |
| 15 | An error occurred when attempting to read the PPT block to ensure that no other nucleus is currently using the same PLOG. |
| 18 | An error was detected in the PLOG data set name when attempting to compare the current entry against other active entries in the cluster. |
| 20 | An internal error occurred attempting to initialize the PPT. Please contact your Adabas support representative supplying the DDPRINT and dump from the current session, a PPTPRINT, and the DDPRINT from the previous session. |

PARM ERROR 42

Explanation Error detected during system open:

- error writing PPT RABN; or
- a Work data set was already in use by another nucleus.

PARM ERROR 43

Explanation Error detected during system open:

- either a PLOG was supplied that was different from the one used in the previous session, or no PLOG was supplied. The PLOG from the previous session has not yet been copied.
- PLOGRQ=FORCE was specified and either the PLOG from the previous session has not yet been copied or a UEX2 or UEX12 has not been specified.

PARM ERROR 44

Explanation A noncluster nucleus attempted to start after a cluster failure; or, the first cluster nucleus is starting but there are already active blocks in the PPT. The nucleus is not allowed to start. Switching from single-nucleus mode to multi-nucleus cluster mode or from multi-nucleus cluster mode to single-nucleus mode is not allowed after an abnormal session termination.

PARM ERROR 45

Explanation GETMAIN above the 16MB line failed; memory-related parameters probably too big.

PARM ERROR 46

Explanation UQE could not be generated.

Action Increase NU parameter.

PARM ERROR 47

Explanation An I/O error occurred when reading or writing to the Work data set for one of the following reasons:

- The GCB doesn't match the actual size of the Work data set
- ADARUN LP is larger than the Work data set,
- ADADEF NEWWORK was not run after allocating a new Work data set

The RABN that was to be read or written is printed.

PARM ERROR 48

Explanation An error occurred during checkpoint generation:

- the takeover of checkpoints generated by offline utilities failed; or
- creation of the session start checkpoint failed.

PARM ERROR 49

Explanation An I/O error occurred while reading or writing dual or multiple PLOGs. The RABN that was to be read or written is printed.

PARM ERROR 50

Explanation Dual or multiple PLOG contains data from another database.

PARM ERROR 51

Explanation Parameter conflict: READONLY=YES is not permitted with UTIONLY=YES.

PARM ERROR 52

Explanation No dual or multiple PLOG available for protection logging. All PLOGs are due to be copied.

PARM ERROR 53

Explanation At least one of the specified PLOG data sets is already in use by another nucleus in the cluster.

PARM ERROR 54

Explanation IGNDIB=YES was specified but the DIB does not contain a conflicting nucleus or utility entry.

Action Remove the IGNDIB parameter.

PARM ERROR 55

Explanation Error while attempting to lock or unlock a global resource. An ADAN54 message preceding this parameter error indicates the specific global resource that could not be locked/unlocked.

PARM ERROR 56

Explanation A DIB entry was found with an inconsistent group name. The associated nucleus may still be active. The DIB entry can be removed only by a nucleus of the same type (single, cluster) and the same CLUGROUPNAME as the DIB entry's owner.

PARM ERROR 57

Explanation DIB entry missing. Another cluster nucleus is already active on this database, but its DIB entry is not present.

PARM ERROR 58

Explanation The Work block size is too small to store the maximum compressed data record permitted in this database according to MAXRECL definition.

Action Increase the Work block length.

PARM ERROR 59

Explanation The Work block size is too small for the largest Associator block size present in this database.

PARM ERROR 60

Explanation The PLOG block size is too small to store the maximum compressed data record permitted in this database according to MAXRECL definition.

PARM ERROR 61

Explanation Important fields in the GCBs changed while this nucleus was starting. The nucleus is not able to handle this situation.

Action Restart the nucleus.

PARM ERROR 62

Explanation CPU timer initialization failed.

PARM ERROR 63

Explanation RRDF=YES is not allowed. Note that the RRDF/ENET option for maintaining shadow databases is currently unavailable for cluster nuclei.

PARM ERROR 64

Explanation An attempt was made to start a version 7.2 or above nucleus without first formatting the protection logs (PLOGs). PLOGs must be formatted when converting to version 7.2 or above.

PARM ERROR 65

Explanation The ADARUN statement's NSISN parameter value is greater than the allowed maximum of $(\text{Work block size} - 6) / 4$.

PARM ERROR 66

Explanation The ADARUN statement's LU parameter specifies a value greater than the byte count implied by the NAB (number of attached buffers) parameter. The error was detected during open operation.

PARM ERROR 67

Explanation Initialization failed for DTP=RM or DTP=TM either because of conflicts in the DTP (distributed transaction processing) ADARUN parameter settings (perhaps with the MODE, READONLY, or LOCAL parameter settings as well) or because of problems with the DDWORKR4/WORKR4 data set used in transaction management. For more information, read about the DTP ADARUN parameter in the *Adabas Operations Manual* and the DDWORKR4/WORKR4 data set in *Adabas DBA Tasks*.

Action Review the message(s) that precede this parameter error to determine the cause and resolution of the problem.

PARM ERROR 68

Explanation If you have Adabas Transaction Manager version 7.4 or earlier installed, an invalid parameter was specified with DTP=TM:

- single user mode (MODE=SINGLE) is not allowed.
- LOCAL=YES is not allowed.
- READONLY=YES is not allowed.
- LDTP (Work part 4) specified with a nonzero value is not allowed.

If it is necessary for some reason to hold data about incomplete transactions in the TM, LDTP with a nonzero value can be specified but IGNDTP=YES must also be specified. The IGNDTP parameter is for emergency use only and should only be used in consultation with your Software AG technical support representative.



Warning:

Whenever the data on Work part 4 is ignored, the integrity of the incomplete global transactions that are related to that data cannot be guaranteed.

If you have Adabas Transaction Manager version 7.5 or later installed, an invalid parameter was specified with DTP=TM:

- single user mode (MODE=SINGLE) is not allowed.
- LOCAL=YES is not allowed.
- READONLY=YES is not allowed.

PARM ERROR 69

Explanation The value specified for the DTP parameter is invalid.

Action Specify "RM" or "TM" or "NO".

PARM ERROR 70

Explanation Error during generation of predefined formats:

- Reading system-file FCB or FDT failed;
- Translating internal format failed; or
- Pool for system-internal formats is too small.

PARM ERROR 71

Explanation If you have Adabas Transaction Manager version 7.4 or earlier installed, an invalid parameter was specified with NUCID:

- MODE=SINGLE is not allowed.
- READONLY=YES is not allowed.
- LFIOP must be nonzero.
- If protection logs are used, dual or multiple PLOGs must be specified.
- MXMSG must be between 1 and 32767.
- NUCID must not equal UBID.

If you have Adabas Transaction Manager version 7.5 or later installed, an invalid parameter was specified with NUCID:

- MODE=SINGLE is not allowed.
- READONLY=YES is not allowed.
- LFIOP must be nonzero.
- If protection logs are used, dual or multiple PLOGs must be specified.
- MXMSG must be between 1 and 32767.
- NUCID must not equal UBID.

PARM ERROR 72

Explanation Initialization of recovery logging failed.

PARM ERROR 73

Explanation Response code 75 (ADARSP075) or 77 (ADARSP077) was received because the checkpoint file is full. Checkpoints from offline utilities may have been lost.

Action Start the nucleus with UTIONLY=YES and reorder/increase the checkpoint file.

PARM ERROR 74

Explanation The database will not start until the PLOG data sets have been copied or reformatted. Most likely, the database was restored and the PLOG data sets had not yet been copied. They still may be needed for the regenerate function.

Action If the contents of the PLOG data sets are needed for a possible future regenerate function, run ADARES PLCOPY to copy them off. If the PLOGs are not needed, reformat them using the ADAFRM PLOGFRM function. In either case, start the nucleus after freeing the PLOG data sets.

PARM ERROR 75

Explanation The nucleus cannot run with the recovery log (RLOG) feature if it runs without PLOG or if PLOGRQ=SEL is specified. The protection log (PLOG) data set is not available; that is, PLOGRQ=SEL or PLOGRQ=NO is specified.

PARM ERROR 76

Explanation The nucleus was started with DTP=TM or DTP=NO, but Work Part 4 contains data about in-doubt transactions.

Action Start the nucleus with DTP=RM.

PARM ERROR 77

Explanation Machine clock (STCK) problem. The system was IPLed with the clock not set and running or set to an invalid date.

Action Correct the date (timestamp) and restart the nucleus.

PARM ERROR 78

Explanation Work part 2 has become too small because Work part 4 contains two-phase commit data that must be retained.

PARM ERROR 79

Explanation The ENET user exit 10 is missing.

PARM ERROR 80

Explanation ADACLU initialization failed and the nucleus terminated. A preceding PLX*nnn* message from ADACLU provided more detailed information.

Action Refer to the explanation and action of the preceding PLX*nnn* message.

PARM ERROR 81

Explanation A read-only (READONLY=YES) or single-user (MODE=SINGLE) nucleus cannot start if DTP=RM is specified.

PARM ERROR 82

Explanation During session open, the system detected that a Delta Save logging (DLOG) area was installed but parameter DSF was not set to YES. DSF=YES must be specified to run with the Delta Save Facility.

Action Restart the nucleus with parameter DSF=YES.

Alternatively, restart the nucleus with parameter DSF=NO; the nucleus then removes the DLOG area and runs in non-Delta Save mode.

**Warning:**

After switching to non-Delta Save mode, it is not longer possible to perform delta save operations.

PARM ERROR 83

Explanation Initialization of the Delta Save Facility failed. A preceding Delta Save operator message indicates the cause of the failure.

Action Check messages from ADADSF.

PARM ERROR 84

Explanation The DSF logging area could not be removed. Another Adabas cluster nucleus is already running with Delta Save Facility active.

Action Start the nucleus with DSF=YES.

PARM ERROR 85

Explanation The previous nucleus session terminated with Work overflow. The nucleus has no free space on Work part 1 for protection information that will be produced during session autorestart.

Action In a cluster environment (Adabas Cluster Services or Parallel Services), start a different cluster nucleus (possibly a new one) with sufficient free space on Work part 1. In a non-cluster environment (base Adabas), restore and regenerate the database.

PARM ERROR 86

Explanation VOL-SER table could not be established.

PARM ERROR 87

Explanation Entire Conversion Services (ECS) initialization failed.

PARM ERROR 88

Explanation A database that uses Universal Encoding Support (UES) needs a version 7 or above Adabas router. If the database uses UES features, it cannot work with an Adabas router (ADASVC) version 6.2 or below.

Action Install a version 7.1 or above router (ADASVC).

PARM ERROR 90

Explanation Invalid ADATCP configuration or UES=NO. Running with TCPIP=YES requires universal encoding support.

Action Check and correct, if necessary, the TCPURL parameter. Install UES and specify UES=YES.

PARM ERROR 91

Explanation Adabas cluster initialization failed. Either the program was not running authorized or the GETMAIN failed.

Action Ensure that the program is APF-authorized. Review the space requirements for your system. If you are unable to determine the problem, contact your Software AG technical support representative.

PARM ERROR 92

Explanation During session open, an attempt to join the Adabas cluster communication group failed. This error initializing the Adabas cluster messaging service is preceded by other messages explaining the specific error.

PARM ERROR 93

Explanation Connect to lock structure failed.

Action Review the lock structure definition requirements. If you are unable to determine the problem, contact your Software AG technical support representative.

PARM ERROR 94

Explanation Connect to cache structure failed.

Action Review the cache structure definition requirements. If you are unable to determine the problem, contact your Software AG technical support representative.

PARM ERROR 95

Explanation Communication with other active Adabas cluster nuclei failed.

Action Review the requirements for communication between cluster nuclei running on the same operating system image and between operating system images running members of the cluster. If you are unable to determine the problem, contact your Software AG technical support representative.

PARM ERROR 96

Explanation Inconsistent structure name. Another Adabas cluster nucleus is already running with a different CLUCACHENAME or CLULOCKNAME parameter.

Action Ensure that all nuclei in a sysplex cluster use the same coupling facility cache and lock structure names.

PARM ERROR 97

Explanation Incompatible global parameters. Another Adabas cluster nucleus is already running with incompatible global parameters that cannot be modified online.

Action Reset nonmodifiable global ADARUN parameters the same for all cluster nuclei. You may be required to stop nuclei, change the parameter settings, and restart.

PARM ERROR 98

Explanation Locking/unlocking an Adabas cluster resource failed.

Action Contact your Software AG technical support representative.

PARM ERROR 99

Explanation Internal error.

Action Contact your Software AG technical support representative.

PARM ERROR 100

Explanation There are more than 31 nuclei in an Adabas Parallel Services cluster; this is not allowed.

Action Reconfigure your Adabas Parallel Services cluster so that you have 31 or fewer participating Adabas nuclei.

PARM ERROR 101

Explanation Invalid parameters specified with CLOGMRG=YES; LOGGING=YES is required; dual or multiple CLOGs are required.

Action Specify the correct ADARUN parameters and restart the session.

PARM ERROR 102

Explanation A cluster nucleus was started after abnormal termination with a different WORK data set. The PPT indicates that the previously used WORK data set still contains data, but this Cluster Service or Parallel Service nucleus was started with a different WORK data set.

Action Restart the cluster nucleus with the previously used WORK data set. Change the WORK data set only after normal termination.

PARM ERROR 103

Explanation Incompatible usage of dual PLOG data sets.

If the first active nucleus uses PLOG data sets, all subsequent nuclei *must* use PLOG data sets. If the first active nucleus does not use PLOG data sets, all subsequent nuclei *must not* use PLOG data sets.

PARM ERROR 104

Explanation Incompatible usage of UEX2 or UEX12.

If the first active nucleus uses either UEX2 or UEX12, all subsequent nuclei *must* use either UEX2 or UEX12. If the first active nucleus does not use UEX2 or UEX12, all subsequent nuclei must *not* use UEX2 or UEX12.

PARM ERROR 105

Explanation Improper configuration of Global Resource Serialization (GRS). A resource lock acquired by this nucleus was ineffective against a peer nucleus.

Action Contact your system programmer to ensure that GRS is configured in a way that GRS resource locks are mutually effective against one another on all systems on which you intend to run Cluster Services nuclei.

PARM ERROR 106

Explanation When LOCAL=YES is specified, all cluster nuclei for a database must start on the same system.

Action If LOCAL=YES is the intended parameter setting, start all cluster nuclei for the database on the same system. Otherwise, change the parameter setting to LOCAL=NO.

PARM ERROR 109

Explanation The Adabas nucleus tried to load a valid license module (load module ADALIC), but errors occurred. Other error messages providing more information about the error accompany this nucleus startup error

Action Verify that you have received a valid Adabas license (via installation tape or e-mail) and that it was installed correctly, according to the Adabas database installation steps specific to your operating environment. If problems persist, contact your Software AG technical support representative for assistance.

PARM ERROR 110

Explanation An error occurred when the Adabas nucleus called a hyperexit for initialization.

Action Investigate the response code and subcode to determine the reason for the error.

PARM ERROR 111

Explanation A parameter value for cluster nuclei is invalid:

- MXCANCEL must be between 15 and 2,147,483,647 seconds.
- MXCANCELWARN must be zero (0) or between 4 and (MXCANCEL–1) seconds.
- MXMSG must be between 15 and 32,767 seconds.
- MXMSGWARN must be zero (0) or between 4 and (MXMSG–1) seconds.
- MXSTATUS must be zero (0) or between 15 and 21,474,836 seconds.
- MXWTOR must be zero (0) or between 15 and 64,800 seconds.

Action Correct the invalid parameter value to one of the valid values listed above.