

Subprograms

You will now expand your program to include a `CALLNAT` statement that invokes a subprogram. In the subprogram, the employees identified from the main program will be the basis of a `FIND` request to the `VEHICLES` file which is also part of the demo database. As a result, your output will contain vehicles information from the subprogram as well as employees information from the main program.

The new subprogram requires the creation of an additional local data area and a parameter data area.

When you have completed the exercises below, your sample application will consist of the following modules:



This chapter contains the following exercises:

- Modifying the Local Data Area
- Creating a Parameter Data Area from an Existing Local Data Area
- Creating Another Local Data Area Containing a Different View
- Creating a Subprogram
- Referencing the Subprogram from Your Program

Modifying the Local Data Area

You will now add more fields to the local data area that you have previously created. These fields will be used by the subprogram that you will create later.

▶ To add more fields to the local data area

1. Return to your local data area.

```
E LDA01
```

2. Define the following fields below #NAME-END:

Level (L column)	Name	Format (F column)	Length
1	#PERS-ID	A	8
1	#MAKE	A	20
1	#MODEL	A	20

The local data area should now look as follows:

```
Local      LDA01      Library TUTORIAL      DBID 11177 FNR      8
Command
I T L Name                      F Length      Miscellaneous
All  --  ----->
      1 #NAME-START                A      20
      1 #NAME-END                  A      20
      1 #PERS-ID                    A       8
      1 #MAKE                       A     20
      1 #MODEL                      A     20

----- S 5      L 1
```

3. Stow the local data area.

Creating a Parameter Data Area from an Existing Local Data Area

A parameter data area (PDA) is used to specify the data parameters to be passed between your Natural program and the subprogram that you will create later. The parameter data area will be referenced in the subprogram.

With minor modifications, your local data area can be used to create the parameter data area: you will delete two of the data fields in the local data area and then save the revised data area as a parameter data area. The original local data area remains intact.

▶ **To create the parameter data area**

1. In the local data area, delete the fields #NAME-START and #NAME-END.
2. Enter the following in the command line of the data area editor.

```
SA PDA01
```

The current data area is saved with the new name PDA01. The existing local data area is still shown in the editor.

3. Load the newly created data area into the editor by entering the following command:

```
E PDA01
```

4. To change the local data area into a parameter data area, enter the following command:

```
SET TYPE A
```

where "A" denotes parameter data area.

The object type changes to "Parameter". This is indicated at the top left of the screen. The parameter data area should now look as follows:

I T L	Name	F Length	Miscellaneous
All	----->		
1	#PERS-ID	A 8	
1	#MAKE	A 20	
1	#MODEL	A 20	
			S 3 L 1

5. Stow the parameter data area.

Creating Another Local Data Area Containing a Different View

You will now create a second local data area and import fields from the DDM for the VEHICLES database file.

This local data area will be referenced in the subprogram.

▶ To create the local data area

1. Enter the following command in the command line of the data area editor.

```
CLEAR
```

The data area editor is now empty.

2. To change the type of the data area, enter the following in the command line:

```
SET TYPE L
```

where "L" denotes local data area.

3. In the first line of the editing area, enter the following starting in the **T** column:

```
.V(VEHICLES)
```

4. Press ENTER.

The VEHICLES view appears.

```

SYSGDA 4461: Mark fields to incorporate into data area.
Local          Library TUTORIAL          DBID 11177 FNR      8
View VEHICLES
I T L Name          F Length  Miscellaneous
-----
      2 REG-NUM      A         15 /* CAR'S REGISTR. NUMBE
      2 CHASSIS-NUM  I          4 /* MANUFACTURER NUMBER
      2 PERSONNEL-ID A          8 /* IDENT. OF CAR USER
G    2 CAR-DETAILS  / * DESCRIPTION OF THE C
      3 MAKE         A         20
      3 MODEL        A         20
      3 COLOR        A         10
      3 COLOUR       A         10
      2 YEAR         N         4.0 /* MANUFACTURING YEAR
      2 CLASS        A          1 /* P=PRIVAT
      2 LEASE-PUR    A          1 /* L=LEASED
      2 DATE-ACQ     N         8.0 /* DATE THE CAR WAS ACQ
      2 CURR-CODE    A          3 /* CURRENCY OF CAR COST
M    2 MAINT-COST   P         7.0 (1:60)/* MAINTENANCE COST
      2 MODEL-YEAR-MAKE A         24 /* YEAR + CAR MAKE /* SP
-----

```

5. Mark the following fields by entering any character in the **I** column :

```

PERSONNEL-ID
CAR-DETAILS
MAKE
MODEL

```

6. After you have marked all required fields, press ENTER to return to the data area editor.

The local data area should now look as follows:

Local Command	Library	TUTORIAL	DBID	11177	FNR	8
I T L	Name	F Length	Miscellaneous			> +
All	----->					
V 1	VEHICLES-VIEW		VEHICLES			
2	PERSONNEL-ID	A	8 /* IDENT. OF CAR USER			
G 2	CAR-DETAILS		/* DESCRIPTION OF THE CAR			
3	MAKE	A	20			
3	MODEL	A	20			
						----- S 5 L 1

7. Save the new local data area by entering the following in the command line:

```
SA LDA02
```

8. Stow the new local data area.

Creating a Subprogram

You will now create a subprogram that uses a parameter data area and a local data area to retrieve information from the VEHICLES file. The subprogram receives the personnel ID passed by the program PGM01 and uses this ID as the basis for a search of the VEHICLES file.

To create the subprogram

1. In the command line of the data area editor, enter the following command:

```
E N
```

where "N" denotes subprogram.

An empty program editor is invoked. The object type has been set to subprogram.

2. Enter the following:

```
DEFINE DATA
  PARAMETER USING PDA01
  LOCAL USING LDA02
END-DEFINE
*
```

```

FD1. FIND (1) VEHICLES-VIEW
    WITH PERSONNEL-ID = #PERS-ID
    MOVE MAKE (FD1.) TO #MAKE
    MOVE MODEL (FD1.) TO #MODEL
    ESCAPE BOTTOM
END-FIND
*
END

```

This subprogram returns to a given personnel ID the make and model of the employee's company car.

The FIND statement selects a set of records (here: one record) from the database based on the search criterion #PERS-ID.

In the field #PERS-ID, the subprogram receives the value of PERSONNEL-ID that has been passed by the program PGM01. The subprogram uses this value as the basis for a search of the VEHICLES file.

3. Stow the subprogram.

```
STOW SPGM01
```

Referencing the Subprogram from Your Program

A subprogram is invoked from the main program using a CALLNAT statement. A subprogram can only be invoked via a CALLNAT statement; it cannot be executed by itself. A subprogram has no access to the global data area used by the invoking object.

Data is passed from the main program to the specified subprogram through a set of parameters that are referenced in the DEFINE DATA PARAMETER statement of the subprogram.

The variables defined in the parameter data area of the subprogram do not have to have the same names as the variables in the CALLNAT statement. Since the parameters are passed by address, it is only necessary that they match in sequence, format, and length.

You will now modify your main program so that it can use the subprogram you have just defined.

To use the subprogram in your main program

1. Return to the program editor by entering the following in the command line.

```
E PGM01
```

2. Insert the following directly above the DISPLAY statement:

```

RESET #MAKE #MODEL
CALLNAT 'SPGM01' PERSONNEL-ID #MAKE #MODEL

```

The RESET statement sets the values of #MAKE and #MODEL to null values.

3. Delete the line containing the DISPLAY statement and replace it with the following:

```
WRITE TITLE
  / '*** PERSONS WITH 20 OR MORE DAYS LEAVE DUE ***'
  / '*** ARE MARKED WITH AN ASTERISK ***'//
*
DISPLAY  1X '//NAME' NAME
         1X '//DEPT'  DEPT
         1X '/LV/DUE' LEAVE-DUE
         ' '          #MARK
         1X '//MAKE'  #MAKE
         1X '//MODEL' #MODEL
```

The text defined with the WRITE TITLE statement will appear at the top of each page in the output. The WRITE TITLE statement overrides the default page title: the information which was previously displayed at the top of each page (page number, date and time) is no longer shown. Each slash (/) causes the subsequent information to be shown in a new line.

Since the subprogram is now returning additional vehicles information, the columns in the output need to be resized. They receive shorter headers. The column in which the asterisk is to be shown (#MARK), does not receive a header at all. One space will be inserted between the columns (1X). Each slash in the header causes the subsequent information to be shown in a new line of the same column.

Your program should now look as follows:

```
DEFINE DATA
  GLOBAL USING GDA01
  LOCAL USING LDA01
END-DEFINE
*
RP1. REPEAT
*
  INPUT USING MAP 'MAP01'
*
  IF #NAME-START = '.' THEN
    ESCAPE BOTTOM (RP1.)
  END-IF
*
  IF #NAME-END = ' ' THEN
    MOVE #NAME-START TO #NAME-END
  END-IF
*
  RD1. READ EMPLOYEES-VIEW BY NAME
        STARTING FROM #NAME-START
        ENDING AT #NAME-END
*
  IF LEAVE-DUE >= 20 THEN
    PERFORM MARK-SPECIAL-EMPLOYEES
  ELSE
    RESET #MARK
  END-IF
*
  RESET #MAKE #MODEL
  CALLNAT 'SPGM01' PERSONNEL-ID #MAKE #MODEL
*
  WRITE TITLE
    / '*** PERSONS WITH 20 OR MORE DAYS LEAVE DUE ***'
```



```

/ '*** ARE MARKED WITH AN ASTERISK ***' //
*
DISPLAY 1X '//NAME' NAME
        1X '//DEPT' DEPT
        1X '//LV/DUE' LEAVE-DUE
        ' ' #MARK
        1X '//MAKE' #MAKE
        1X '//MODEL' #MODEL
*
END-READ
*
IF *COUNTER (RD1.) = 0 THEN
  REINPUT 'No employees meet your criteria.'
END-IF
*
END-REPEAT
*
END

```

4. Run the program.
5. Enter "JONES" as the starting name and press ENTER.

The resulting list should look similar to the following:

MORE

```

*** PERSONS WITH 20 OR MORE DAYS LEAVE DUE ***
*** ARE MARKED WITH AN ASTERISK ***

```

N A M E	DEPT	LV DUE	MAKE	MODEL
JONES	SALE30	25 *	CHRYSLER	IMPERIAL
JONES	MGMT10	34 *	CHRYSLER	PLYMOUTH
JONES	TECH10	11	GENERAL MOTORS	CHEVROLET
JONES	MGMT10	18	FORD	ESCORT
JONES	TECH10	21 *	GENERAL MOTORS	BUICK
JONES	SALE00	30 *	GENERAL MOTORS	PONTIAC
JONES	SALE20	14	GENERAL MOTORS	OLDSMOBILE
JONES	COMPL2	26 *	DATSUN	SUNNY
JONES	TECH02	25 *	FORD	ESCORT 1.3

6. To return to the program editor, enter EDIT at the MORE prompt.
7. Stow the program.

You have successfully completed this tutorial.