

# FUSER - Natural System File for User Programs

This Natural profile parameter defines five subparameters for the Natural user-program system file. This system file is the database file from which all user-written Natural programs are retrieved.

For information on system files, refer to: *System Files* in the *Operations* documentation.

<b>Possible settings</b>	<i>database-ID</i>	1-254	Database ID 255 is reserved for logical system files for Software AG products, see profile parameter <code>LFILE</code> .
	<i>file-number</i>	1-255	File number.
	<i>password</i>	1 to 8 characters	The password is only required if the Natural user-program system file has been password-protected using the Adabas security feature.  The password is reserved for future use; currently, it is ignored.
	<i>cipher-key</i>	1 to 8 numeric digits	The cipher key is only required if the Natural user-program system file has been ciphered using the Adabas security feature.  The cipher key is reserved for future use; currently, it is ignored.
	RO		Read-only option.  RO indicates that the Natural user-program system file is "read-only" and is only specified if modifications on the file are to be disabled.
<b>Default setting</b>	none		
<b>Dynamic specification</b>	yes		
<b>Specification within session</b>	no		

The syntax of this parameter is:

```
FUSER=(database-ID,file-number,password,cipher-key,RO)
```

**Examples:**

FUSER=( 22, 5 )

FUSER=( 22, 5 , , , RO )

FUSER=( 22, 5 , PASSW2 )