


# WRITE TITLE



This chapter covers the following topics:

- Function
- Restrictions
- Syntax Description
- Example

For an explanation of the symbols used in the syntax diagram, see *Syntax Symbols*.

Related Statements: AT END OF PAGE | AT TOP OF PAGE | CLOSE PRINTER | DEFINE PRINTER | DISPLAY | EJECT | FORMAT | NEWPAGE | PRINT | SKIP | SUSPEND IDENTICAL SUPPRESS | WRITE | WRITE TRAILER

Belongs to Function Group: *Creation of Output Reports*

---

## Function

The WRITE TITLE statement is used to override the default page title with a page title of your own. It is executed whenever a new page is initiated.

See also the following sections in the *Programming Guide*:

- *Controlling Data Output*
- *Report Specification - (rep) Notation*
- *Layout of an Output Page*
- *Page Titles, Page Breaks, Blank Lines*
- *Define Your Own Page Title - WRITE TITLE Statement*
- *Text Notation*

## Processing

This statement is non-procedural, that is, its execution depends on an event, not on where in a program it is located.

If a report is produced by statements in different objects, the WRITE TITLE statement is only executed if it is contained in the same object as the statement that causes a new page to be initiated.

## Restrictions

- WRITE TITLE may be specified only once per report.
- WRITE TITLE cannot be specified within a special condition statement block.
- WRITE TITLE cannot be specified within a subroutine.

## Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S A G N	A U N P I F B D T L G O	yes	no
<i>operand2</i>	C S	N P I B	yes	no

Syntax Element Description:

Syntax Element	Description
<i>(rep)</i>	<p><b>Report Specification:</b></p> <p>If multiple reports are to be produced, the notation <i>(rep)</i> may be used to specify the identification of the report for which the WRITE TITLE statement is applicable.</p> <p>As report identification, a value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified.</p> <p>If <i>(rep)</i> is not specified, the WRITE TITLE statement applies to the first report (Report 0).</p> <p>For information on how to control the format of an output report created with Natural, see <i>Controlling Data Output</i> (in the <i>Programming Guide</i>).</p>

Syntax Element	Description
LEFT JUSTIFIED UNDERLINED	<p><b>Page Title Justification and/or Underlining:</b></p> <p>By default, page titles are centered and not underlined. LEFT JUSTIFIED and UNDERLINED may be specified to override these defaults.</p> <p>If UNDERLINED is specified, the underlining character (system default or specified with the session parameter UC (Underlining Character) in a FORMAT statement) is printed underneath the title and runs the width of the line size (see session parameter LS).</p> <p>Natural first applies all spacing or tab specifications and creates the line before centering the whole line. For example, a notation of 10T as the first element would cause the centered header to be positioned five positions to the right.</p>
<i>statement-parameters</i>	<p><b>Parameter Definition at Statement Level:</b></p> <p>One or more parameters, enclosed within parentheses, may be specified at statement level, that is, immediately after the WRITE TITLE statement. Each parameter specified in this manner will override the corresponding parameter previously specified in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement.</p> <p>If more than one parameter is specified, one or more blanks must be present between each entry. An entry may not be split between two statement lines.</p> <p><b>Note:</b> The parameter settings applied here will only be regarded for variable fields, but they have no effect on text-constants. If you would like to set field attributes for a text-constant, they have to be set explicitly for this element, see <i>Parameter Definition at Element (Field) Level</i>.</p> <p>For information on which parameters may be used, see <i>List of Parameters</i> (in the WRITE statement documentation).</p>
<i>nX</i> <i>nT</i> <i>x/y</i>	<p><b>Format Notation and Spacing Elements:</b></p> <p>See <i>Format Notation and Spacing Elements</i> (below).</p>
'text' 'c' (n) <i>attributes</i>	<p><b>Text/Attribute Assignment:</b></p> <p>See <i>Text/Attribute Assignments</i> (below).</p>
<i>operand1</i>	<p><b>Field to Be Displayed in Title:</b></p> <p><i>operand1</i> represents the field(s) to be displayed within the title.</p>

Syntax Element	Description
<i>parameters</i>	<p><b>Parameter Definition at Element (Field) Level:</b></p> <p>One or more parameters, enclosed within parentheses, may be specified at element (field) level, that is, immediately after <i>operand1</i>. Each parameter specified in this manner will override the corresponding parameter previously specified at statement level or in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement.</p> <p>If more than one parameter is specified, one or more blanks must be present between each entry. An entry may not be split between two statement lines.</p> <p>For information on which parameters may be used, see <i>List of Parameters</i> (in the WRITE statement documentation).</p>
SKIP <i>operand2</i> LINES	<p><b>Lines to Be Skipped:</b></p> <p>SKIP may be used to cause lines to be skipped immediately after the title line. The number of lines to be skipped may be specified in <i>operand2</i> as a numeric constant or as the content of a numeric variable.</p> <p><b>Note:</b> SKIP after WRITE TITLE is always interpreted as the SKIP clause of the WRITE TITLE statement, and not as an independent statement. If you wish an independent SKIP statement after a WRITE TITLE statement, use a semicolon (;) to separate the two statements from one another.</p>

### Format Notation and Spacing Elements

Syntax Element	Description
<i>nX</i>	<p><b>Column Spacing:</b></p> <p>This notation inserts <i>n</i> spaces between columns.</p>
<i>nT</i>	<p><b>Tab Setting:</b></p> <p>The <i>nT</i> notation causes positioning (tabulation) to print position <i>n</i>. Backward positioning is not permitted.</p>
<i>x/y</i>	<p><b><i>x/y</i> Positioning:</b></p> <p>Causes the next element to be placed <i>x</i> lines below the output of the last statement, beginning in column <i>y</i>. <i>y</i> must not be zero. Backward positioning in the same line is not permitted.</p>

## Text/Attribute Assignments

Syntax Element	Description
'text'	<b>Text Assignment:</b> The character string enclosed by single quotes is displayed.
'c'(n)	<b>Character Repetition:</b> The character enclosed by single quotes is displayed <i>n</i> times immediately before the field value.
attributes	<b>Field Representation and Color Attributes:</b> It is possible to assign various attributes for text/field display. These attributes and the syntax that may be used are described in the section <i>Output Attributes</i> below.  Examples:  WRITE TITLE 'TEXT' (BGR) WRITE TITLE 'TEXT' (B) WRITE TITLE 'TEXT' (BBLC)

## Output Attributes

*attributes* indicates the output attributes to be used for text display. Attributes may be:

$\left\{ \left\{ \begin{array}{l} \mathbf{AD}=\mathbf{AD}\text{-value} \dots \\ \mathbf{CD}=\mathbf{CD}\text{-value} \dots \\ \mathbf{PM}=\mathbf{PM}\text{-value} \dots \end{array} \right. \right\} \dots$	$\left. \right\}$

For the possible session parameter values, refer to the corresponding sections in the *Parameter Reference* documentation:

- *AD - Attribute Definition*, section *Field Representation*
- *CD - Color Definition*
- *PM - Print Mode*

### Note:

The compiler actually accepts more than one attribute value for an output field. For example, you may specify: AD=BDI. In such a case, however, only the last value applies. In the given example, only the value I will become effective and the output field will be displayed intensified.

## Example

```

** Example 'WTIEX1': WRITE (with TITLE option)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 CITY
  2 JOB-TITLE
END-DEFINE
*
*
FORMAT LS=70
*
WRITE TITLE LEFT JUSTIFIED UNDERLINED
      *TIME 3X 'PEOPLE LIVING IN NEW YORK CITY'
      11X 'PAGE:' *PAGE-NUMBER
SKIP 1
*
FIND EMPL-VIEW WITH CITY = 'NEW YORK'
      DISPLAY NAME FIRST-NAME 3X JOB-TITLE
END-FIND
END

```

### Output of Program WTIEX1:

```

09:33:16.5  PEOPLE LIVING IN NEW YORK CITY          PAGE:      1
-----
          NAME                FIRST-NAME                CURRENT
                               POSITION
-----
RUBIN                SYLVIA                SECRETARY
WALLACE              MARY                ANALYST

```