

Natural for Ajax

Responsive Natural Page Layout

Version 9.3.1

September 2025

This document applies to Natural for Ajax Version 9.3.1 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2009-2025 Software GmbH, Darmstadt, Germany and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software GmbH product names are either trademarks or registered trademarks of Software GmbH and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software GmbH and/or its subsidiaries is located at https://softwareag.com/licenses.

Use of this software is subject to adherence to Software GmbH's licensing conditions and terms. These terms are part of the product documentation, located at https://softwareag.com/licenses and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software GmbH Products / Copyright and Trademark Notices of Software GmbH Products". These documents are part of the product documentation, located at https://softwareag.com/licenses and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software GmbH.

Document ID: ONE-NATNJX-PAGELAYOUT-RESPONSIVE-931-20250930

Table of Contents

Responsive Natural Page Layout	v
1 About this Documentation	
Document Conventions	2
Online Information and Support	2
Data Protection	
2 Creating Responsive Pages	5
3 First Steps towards Responsiveness	9
4 Responsive Pages	
BMOBILE:PAGEHEADER	12
BMOBILE:FOOTER	13
BMOBILE:SUBPAGE	15
BMOBILE:SUBCISPAGE	18
BMOBILE:MODAL	21
BMOBILE:INTMODAL, BMOBILE:HELPMODAL,	
BMOBILE:INTMODALHEADER, BMOBILE:INTMODALBODY and	
BMOBILE:INTMODALFOOTER	22
BMOBILE:DYNMODAL	30
5 Responsive Controls	35
BMOBILE:ALERT	36
BMOBILE:BARTEXT	36
BMOBILE:BUTTON	39
BMOBILE:CHECKBOX	42
BMOBILE:COMBOFIX	46
BMOBILE:COMBOGROUP	50
BMOBILE:COMBOOPTION	
BMOBILE:COMBODYN	51
BMOBILE:DATEINPUT2	55
BMOBILE:DROPDOWN	
BMOBILE:DROPDOWNLIST	64
BMOBILE:DROPDOWNHEADER	
BMOBILE:DROPDOWNITEM	
BMOBILE:DROPDOWNSEPARATOR	69
BMOBILE:FFIELD	70
BMOBILE:FLABEL	77
BMOBILE:FTEXTAREA	
BMOBILE:FTEXTOUT	
BMOBILE:GOOGLEMAP	88
BMOBILE:ICON	
BMOBILE:IMAGEOUT	91
BMOBILE:RADIOBUTTON	
BMOBILE:TOGGLER	
6 Responsive Containers	
BMOBILE:CARD	100

BMOBILE:CARDCONTAINER	109
BMOBILE:COL	111
BMOBILE:PANEL	112
BMOBILE:ROW	114
BMOBILE:CONTAINER	115
BMOBILE:FORM, BMOBILE:FORMINLINE	117
BMOBILE:FORMAREA	120
BMOBILE:FORMGROUP	121
BMOBILE:LISTGROUP	123
BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR,	
BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONTALBAR,	
BMOBILE:CONTENT	126
BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB	131
BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES,	
BMOBILE:STRAIGHTTAB and BMOBILE:PAGER	
7 Responsive Grids	147
BMOBILE:ICONCOL	
BMOBILE:SIMPLECOL	150
BMOBILE:SIMPLEGRID	152
BMOBILE:SIMPLEHEADERCOL	157
BMOBILE:SIMPLEHEADERROW	159
BMOBILE:SIMPLEROW	159
8 Responsive Trees	161
BMOBILE:DATATREE	162
9 Responsive Menus	167
BMOBILE:NAVBAR	168
BMOBILE:NAVMENU	170
10 Responsive Chart Controls	173
RCHART and RCHARTDATA	174
RPIECHART	183
11 Responsive Media Controls	189
BMOBILE:VIDEO	190
BMOBILE:MEDIAUPLOAD, BMOBILE:MEDIAPREVIEW,	
BMOBILE:MEDIAPREVIEWBUTTON and	
BMOBILE:MEDIAUPLOADBUTTON	191
BMOBILE:IMAGEFILEUPLOAD, BMOBILE:IMAGEPREVIEW,	
BMOBILE:IMAGEPREVIEWBUTTON and	
BMOBILE:IMAGEUPLOADBUTTON	199
12 Controls for Responsive and Non-Responsive Pages	209
13 Styling a Responsive Page	211
Responsive Pages Basics	
Stylesheets of an NJX Application	
Applying your Specific Application Style	218
Hints	227

Responsive Natural Page Layout

A set of controls and containers for building responsive applications is available. The controls and containers support responsiveness, which means that the pages automatically adapt to various screen sizes. The controls are built with Bootstrap (http://getbootstrap.com/). You will find running samples built with these controls and containers in the Natural Ajax Demos.

Creating Responsive Pages
First Steps towards Responsiveness
Responsive Pages
Responsive Controls
Responsive Containers
Responsive Grids
Responsive Trees
Responsive Menus
Responsive Chart Controls
Responsive Media Controls
Controls for Responsive and Non-Responsive Pages
Styling a Responsive Page

1 About this Documentation

Document Conventions	. 2
Online Information and Support	
Data Protection	

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format folder.subfolder.service, APIs, Java classes, methods, properties.
Italic	Identifies: Variables for which you must supply values specific to your own situation or
	environment. New terms the first time they occur in the text.
	References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{}	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
I	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis ().

Online Information and Support

Product Documentation

You can find the product documentation on our documentation website at https://documentation.softwareag.com.

Product Training

You can find helpful product training material on our Learning Portal at https://learn.software-ag.com.

Tech Community

You can collaborate with Software GmbH experts on our Tech Community website at https://tech-community.softwareag.com. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software GmbH news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories at https://github.com/softwareag and https://github.com/softwareag and discover additional Software GmbH resources.

Product Support

Support for Software GmbH products is provided to licensed customers via our Empower Portal at https://empower.softwareag.com. Many services on this portal require that you have an account. If you do not yet have one, you can request it at https://empower.softwareag.com/register. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.
- Add product feature requests.


Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.


2

Creating Responsive Pages


To create layout pages for responsive applications use one of the **Natural Responsive Page** templates. If you want your application to have a sidebar with navigation menu choose the **Natural Responsive Page - Sidebar** template.



The wizard will create a page layout with responsive containers. The palette shows exactly the controls, which are supported in responsive pages. You can add controls from the palette to your layout in the usual way.



To see the rendering in the preview area set **HTML** as **Layout display mode** in the Ajax Developer properties of your project. The following shows the *mobile_forms.xml* example layout of the Natural Ajax Demos in the Layout Painter.



3

First Steps towards Responsiveness

The responsiveness of a layout is based on style classes. For controls and containers the major responsive style classes are applied automatically, which defines the basic functionality for this control/container in a responsive way.

The responsive sizing of rows and columns in a page is also based on style classes. The basis for this is the **grid system of Bootstrap**. This system allows up to 12 columns across the page. You can specify different dimensions for your rows and columns depending on the devices. This means: Instead of directly applying pixel or percentage width to your controls, you specify style classes defining the number of columns this control is supposed to occupy on a device.

You can add your own additional style classes or style classes supported by the Bootstrap framework to the controls to customize the rendering. The Bootstrap framework contains a variety of ready-to-use classes. For controls and containers, the Layout Painter will offer you the most frequently used classes for this specific control/container.

The best way to get started is by using the Natural Ajax Demos with a large set of simple samples.

4 Responsive Pages

■ BMOBILE:PAGEHEADER	. 12
■ BMOBILE:FOOTER	
■ BMOBILE:SUBPAGE	. 15
■ BMOBILE:SUBCISPAGE	. 18
■ BMOBILE:MODAL	. 21
■ BMOBILE:INTMODAL, BMOBILE:HELPMODAL, BMOBILE:INTMODALHEADER, BMOBILE:INTMODALBODY	
and BMOBILE:INTMODALFOOTER	. 22
■ BMOBILE:DYNMODAL	

BMOBILE:PAGEHEADER

A responsive control to render a page header.

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Sometimes obligatory	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Sometimes obligatory	
	Do not specify a "name" inside the control if specifying a "textid".		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
htmlheading	The rendering of the heading: H1-H6	Optional	h1
			h2
			h3
			h4
			h5
			h6
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	lead
			h1
			h2
			h3

			h4
			h5
			h6
			font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
			navbar-brand
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

BMOBILE:FOOTER

A responsive control to render a page footer.

Properties



Note: The properties for the BMOBILE:FOOTER control are the same as for the BMOBILE:PAGEHEADER control but are implemented using different style sheet classes.

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Sometimes obligatory	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
textid	the control. The "textid" is translated into a corresponding string at runtime.	Sometimes obligatory	
	Do not specify a "name" inside the control if specifying a "textid".		
straighttext	If the text of the control contains HTML tags then these	Optional	true
	are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.		false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
htmlheading	The rendering of the heading: H1-H6	Optional	h1
			h2
			h3
			h4
			h5
			h6
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	lead
			h1
			h2
			h3
			h4
			h5
			h6
			font-italic

			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
			navbar-brand
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Miscellaneou	us		
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:SUBPAGE

A control for responsive embedding of non-Ajax pages or other media.

Basic			
valueprop	Name of the adapter parameter that provides the content of the control.	Optional	
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		

	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
alwaysreload	When setting to false, the subpage is not reloaded when a page switch is executed, default is true.	Optional	true
	1 0		false
			1

aspectratio	Defines the proportional relationship between width and height of the control. Example: 4by3	Optional	
width	Width of the control.	Optional	100
	There are three possibilities to define the width:		120
	(A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of		140
	container controls - it will follow the width that is occupied		160
	by its content.		180
	(B) Pixel sizing: just input a number value (e.g. "100").		200
	(C) Percentage sizing: input a percantage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct		50%
	results if the parent element of the control properly defines a width this control can reference. If you specify this control to have a width of 50% then the parent element (e.g. an		100%
	ITR-row) may itself define a width of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		
height	Height of the control.	Optional	100
	There are three possibilities to define the height:		150
	(A) You do not define a height at all. As consequence the		200
	control will be rendered with its default height. If the control is a container control (containing) other controls then the		250
	height of the control will follow the height of its content.		300
	(B) Pixel sizing: just input a number value (e.g. "20").		250
	(C) Percentage sizing: input a percentage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct		400
	results if the parent element of the control properly defines a height this control can reference. If you specify this control		50%
	to have a height of 50% then the parent element (e.g. an ITR-row) may itself define a height of "100%". If the parent		100%
	element does not specify a width then the rendering result may not represent what you expect.		
Natural	<u> </u>		l
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group	Optional	

	structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	•	

BMOBILE:SUBCISPAGE

A control for responsive embedding of Ajax subpages.

Basic			
valueprop	Name of the adapter parameter that provides the content of the control.	Optional	
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering		
	of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated		
	HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
width	Width of the control.	Optional	100
	There are three possibilities to define the width:		120
			140

			T
	(A) You do not define a width at all. In this case the width		160
	of the control will either be a default width or - in case of container controls - it will follow the width that is occupied		180
	by its content.		200
	(B) Pixel sizing: just input a number value (e.g. "100").		50%
	(C) Percentage sizing: input a percantage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct results if the parent element of the control properly defines a width this control can reference. If you specify this control to have a width of 50% then the parent element (e.g. an ITR-row) may itself define a width of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		100%
height	Height of the control.	Optional	100
	There are three possibilities to define the height:		150
	(A) You do not define a height at all. As consequence the control will be rendered with its default height. If the control		200
	is a container control (containing) other controls then the		250
	height of the control will follow the height of its content.		300
	(B) Pixel sizing: just input a number value (e.g. "20").		250
	(C) Percentage sizing: input a percentage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct		400
	results if the parent element of the control properly defines a height this control can reference. If you specify this control		50%
	to have a height of 50% then the parent element (e.g. an ITR-row) may itself define a height of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		100%
aspectratio	Defines the proportional relationship between width and	Optional	1bv1
1	height of the control. Example: 4by3	1	
			16by9 21by9
			4by3
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*

			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
Natural	,	<u> </u>	
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	-	
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	

BMOBILE:MODAL

A control for responsive embedding of modals. The content of this modal can be any content reachable via a URL. To integrate Natural content, use the BMOBILE:INTMODAL* controls. To open a modal via BMOBILE:BUTTON and BMOBILE:ICON controls apply "modalid: <mymodalid>" as method.

Example

```
<bmobile:button method="modal:mymodalid" ....></bmobile:button>
<bmobile:modal modalid="mymodalid"...></bmobile:modal>
```

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.		
titlename	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
modalid	An id string for the modal. You can use this id in buttons to open the modal. For a modalid mymodalid the methodname in a button is modal:mymodalid.	Optional	
resizable	Per default end-users can resize an open pop-up dialog. Set this property to FALSE if you don't want the end-users to resize the pop-up.	Optional	true false
draggable	Per default open pop-up dialogs are draggable within their parent container. Set this property to FALSE if you don't want the end-users to drag the pop-up.	Optional	true false
pageurl	The url of an html page.	Optional	
pageurlprop	Name of the adapter parameter that dynamically defines the url of an html page.	Optional	
modalbodystyle	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:	Optional	

	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Natural			
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2.	Optional	
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	
Miscellaneous		1	
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:INTMODAL, BMOBILE:HELPMODAL, BMOBILE:INTMODALHEADER, BMOBILE:INTMODALBODY and BMOBILE:INTMODALFOOTER

Use these controls to implement responsive modals. The modals are designed and rendered page internal. You can have any container and control inside the BMOBILE:INTMODALBODY. No separate Adapter is generated for the internal modals. The corresponding fields and events are generated into the Adapter of the page containing the BMOBILE:INTMODAL control. This simplifies data exchange between the parent page and the modal.

To open a modal via BMOBILE:BUTTON and BMOBILE:ICON controls apply "modalid: <mymodalid" as method.

Example

<bmobile:button method="modal:mymodalid"></bmobile:button>
<bmobile:modal modalid="mymodalid"...></bmobile:modal>

- Properties for BMOBILE:INTMODAL
- Properties for BMOBILE:HELPMODAL
- Properties for BMOBILE:INTMODALHEADER
- Properties for BMOBILE:INTMODALBODY
- Properties for BMOBILE:INTMODALFOOTER

Properties for BMOBILE:INTMODAL

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
modalid	An id string for the modal. You can use this id in buttons to open the modal. For a modalid mymodalid the methodname in a button is modal:mymodalid.	Optional	
modalsize	Per default modals have medium size. Set this if you want for instance small size modal-sm, or large size modal-lg.	Optional	modal-sm modal-lg
closeonclick	Per default the pop-up dialog is closed when clicking outside of the pop-up. Set this property to FALSE if you don't want the pop-up dialog to automatically close when clicking outside.	Optional	true false
closeonesc	Per default the pop-up dialog is closed when the escape key is pressed. Set this property to FALSE if you don't want the he pop-up to automatically close when escape is pressed.	Optional	true false
resizable	Per default end-users can resize an open pop-up dialog. Set this property to FALSE if you don't want the end-users to resize the pop-up.	Optional	true false
draggable	Per default open pop-up dialogs are draggable within their parent container. Set this property to FALSE if you don't want the end-users to drag the pop-up.	Optional	true false
centered	Per default a pop-up dialog is centered witin it's parent container. Set this property to FALSE if you don't want the pop-up to be centered.	Optional	true false

Set this property to FALSE if you want to switch off animation. styleclasses CSS style classes separated by a blank. CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Style CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function. Natural njx:natname If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance #FIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2. njx:natstringtype If the control shall be bound to a Natural system variable of string (a MYGRID1.#FIELD2.	Optional	true false
With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function. Natural njx:natname If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2. njx:natstringtype If the control shall be bound to a Natural system variable of string (Optional	
control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function. Natural njx:natname If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD1, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2. njx:natstringtype If the control shall be bound to a Natural system variable of string (Optional	
background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function. Natural njx:natname If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2. njx:natstringtype If the control shall be bound to a Natural system variable of string (
You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function. Natural njx:natname If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD1. njx:natstringtype If the control shall be bound to a Natural system variable of string of the parameter of the parameter of the parameter of the parameter data area of the par		
with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function. Natural njx:natname If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2. njx:natstringtype If the control shall be bound to a Natural system variable of string (strings)		
code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function. Natural njx:natname If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2. njx:natstringtype If the control shall be bound to a Natural system variable of string (
njx:natname If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2. njx:natstringtype If the control shall be bound to a Natural system variable of string (
Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD1 and #GRID1.#FIELD1 and #MYGRID1.#FIELD2. njx:natstringtype If the control shall be bound to a Natural system variable of string (
	Optional	
the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcomment The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	
Miscellaneous	<u> </u>	<u> </u>

testtoolid	Use this attribute to assign a fixed control identifier that can be	Optional	
	later on used within your test tool in order to do the object		
	identification		

Properties for BMOBILE:HELPMODAL

This modal is used for showing online help. It is added automatically to pages in which helpid attributes have been set for controls. The modal is opened automatically on help requests.

Properties for BMOBILE:INTMODALHEADER

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
			bg-warning
			bg-success
			bg-danger
			bg-info
			bg-primary
			bg-secondary
			bg-success
			bg-warning
			bg-dark
			bg-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		

	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
	Do not specify a "name" inside the control if specifying a "textid".		
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
htmlheading	The rendering of the heading: H1-H6	Optional	h1
			h2
			h3
			h4
			h5
			h6
Natural		<u> </u>	
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural	-	

	adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

Properties for BMOBILE:INTMODALBODY

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*

			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Miscellaneo	us		
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

Properties for BMOBILE:INTMODALFOOTER

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	justify-content-center
			justify-content-start
			justify-content-end
			justify-content-*-center
			justify-content-*-start
			justify-content-*-end
			bg-warning

			bg-success
			bg-danger
			bg-info
			bg-primary
			bg-secondary
			bg-success
			bg-warning
			bg-dark
			bg-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Miscellane	bus	<u> </u>	
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:DYNMODAL

This control supports dynamic pop-ups.

As with non-responsive pages, you can also open any responsive page as a pop-up via the Natural PROCESS PAGE MODAL statement. You can customize the rendering and behavior of the pop-up at design-time and dynamically at runtime before the pop-up is opened. Dynamic settings will overwrite design-time settings. From version 9.2.1, each responsive page contains a *BMOBILE:DYNMODAL* control. This control provides the pop-up frame for all pop-ups opened from this page. You can customize this control at design-time.

Hints:

- 1. To have common settings for all pages, you can customize the layout templates. For details, refer to *NaturalONE documentation > Ajax Developer > Getting Started with the Layout Painter > Creating Custom Layout Templates*.
- 2. If you have older responsive layouts which do not contain this BMOBILE:DYNMODAL control yet, you can simply drag this control to the page from the Layout Painter Control Palette.

Design-Time Pop-Up Settings

You can set design-time properties in 2 ways:

- 1. Set the properties popupfeatures, popupheight and popupwidth in the NATPAGE control of the pop-up layout. See *NATPAGE Properties*.
- 2. Set the properties of the BMOBILE:DYNMODAL control in the pop-up parent.

The design-time of the page opened as pop-up will overwrite the BMOBILE:DYNMODAL settings of the pop-up parent.

Dynamic Pop-Up Settings at Runtime

To dynamically customize the pop-up settings at runtime from your Natural program, add an *NJX:XCIOPENPOPUP* control to your parent page. The data structure generated for this control is identical for responsive and non-responsive pages.

Supported Pop-Up Features

Independently whether you specify the features at design-time or at runtime, the following features are supported:

	Values	Default	Description
closeonclick	true/false	true	If true clicking outside the pop-up will close the pop-up
closeonesc	true/false	true	If true pressing the escape key will close the pop-up
resizeable	true/false	true	If true end-users can resize the opened pop-up
draggable	true/false	true	If true end-users can drag the opened pop-up
sizetocontent	true/false	true	If true the pop-up height is automatically sized to the height of the page shown as pop-up
withclosebutton	true/false	true	If true a close button will appear in the header and the footer of the pop-up frame.

In the popupfeatures design-time property (NATPAGE) and the Natural XCIOPENPOPUP.FEA-TURES field you can specify several of these features separated by ";". Example:

XCIOPENPOPUP.FEATURES:='closeonclick:false;closeonesc:false;sizetocontent:true"

Properties for BMOBILE:DYNMODAL

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
modalsize	Per default modals have medium size. Set this if you want for instance small size modal-sm, or large size modal-lg.	Optional	modal-sm modal-lg
sizetocontent	If set to TRUE the pop-up dialog is sized according to the content. If set to FALSE and no direct height/width properties are set, a fixed default size is used. Default is TRUE.	Optional	true false
closeonclick	Per default the pop-up dialog is closed when clicking outside of the pop-up. Set this property to FALSE if you don't want the pop-up dialog to automatically close when clicking outside.	Optional	true false
closeonesc	Per default the pop-up dialog is closed when the escape key is pressed. Set this property to FALSE if you don't want the he pop-up to automatically close when escape is pressed.	Optional	true false
resizable	Per default end-users can resize an open pop-up dialog. Set this property to FALSE if you don't want the end-users to resize the pop-up.	Optional	true false

draggable	Per default open pop-up dialogs are draggable within their parent container. Set this property to FALSE if you don't want the end-users to drag the pop-up.	Optional	true false
withclosebutton	Per default the opened pop-up dialog contains a close button in the footer and in the header. Set this property to FALSE if you don't want close buttons in header of footer of the pop-up.	Optional	true false
centered	Per default a pop-up dialog is centered witin it's parent container. Set this property to FALSE if you don't want the pop-up to be centered.	Optional	true false
animatefade	Per default a fade-in animation is used when the pop-up opens. Set this property to FALSE if you want to switch off animation.	Optional	true false
styleclasses	CSS style classes separated by a blank.	Optional	
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Natural			
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	Optional	
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the	Optional	

	format of the string, A (code page) or U (Unicode). The default is A.		
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification		

5 Responsive Controls

BMOBILE:ALERT	. 36
BMOBILE:BARTEXT	. 36
BMOBILE:BUTTON	. 39
BMOBILE:CHECKBOX	. 42
BMOBILE:COMBOFIX	. 46
BMOBILE:COMBOGROUP	. 50
BMOBILE:COMBOOPTION	. 51
BMOBILE:COMBODYN	
BMOBILE:DATEINPUT2	. 55
BMOBILE:DROPDOWN	
BMOBILE:DROPDOWNLIST	
BMOBILE:DROPDOWNHEADER	. 66
BMOBILE:DROPDOWNITEM	
BMOBILE:DROPDOWNSEPARATOR	
BMOBILE:FFIELD	
BMOBILE:FLABEL	
BMOBILE:FTEXTAREA	
BMOBILE:FTEXTOUT	
BMOBILE:GOOGLEMAP	
BMOBILE:ICON	
BMOBILE:IMAGEOUT	
BMOBILE:RADIOBUTTON	
BMOBILE:TOGGLER	

BMOBILE:ALERT

This control is similar to the STATUSBAR control but more flexible. Use this control to show success or failure of an action.

Properties

Basic			
typeprop	Name of the adapter parameter that provides as value the type of the alert message. The type defines the style in which the alert box is rendered.		
shorttextprop	Name of the adapter parameter that provides as value the message text that is visible inside the alert box.	Obligatory	
longtextprop	Name of the adapter parameter that provides as value the message text that is visible inside the alert box.	Optional	
duration	The duration of the animation in milliseconds.	Optional	500
			1000
			2000
			6000
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	

BMOBILE:BARTEXT

Supports text like headlines in containers like the BMOBILE: HORIZONTALBAR and the BMOBILE: SIDEBAR.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	

textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
	Do not specify a "name" inside the control if specifying a "textid".		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
styleclasses	CSS style classes separated by a blank.	Optional	lead
			h1
			h2
			h3
			h4
			h5
			h6
			font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
			navbar-brand
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		

	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Natural		ll	
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	Optional	
njx:natsysvar	If the control shall be bound to a Natural system variable, this attribute specifies the name of the system variable.	Optional	
njx:natsysio	If the control shall be bound to a Natural system variable with the attribute njx:natsysvar, this attribute indicates if the system variable is modifiable. The default is false.	Optional	
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcv	Name of a Natural control variable that shall be assigned to the control.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:BUTTON

A responsive button.

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
type	The type of the button like reset or submit.	Optional	button submit file reset
renderaslink	If set to "TRUE" the control is rendered as a link.	Optional	true false
renderasicon	Set to TRUE if you specified an icon font without any text. This will render the button like an icon. The margin and padding is reduced and the font-size is adapted.	Optional	true false
renderasbadge	If set to "TRUE" the control is rendered as a badge.	Optional	true false
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
helpid	Help id that is passed to the online help management in case the user presses F1 on the control.	Optional	
Appearance			

styleclasses	CSS style classes separated by a blank.	Optional	btn-default
			btn-primary
			btn-info
			btn-success
			btn-warning
			btn-danger
			btn-sm
			btn-lg
			btn-icon-sm
			btn-icon-lg
			btn-responsive
			btn-outline-primary
			btn-outline-info
			btn-outline-success
			btn-outline-warning
			btn-outline-danger
			close
			mx-auto
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
invisiblemode	This property has three possible values:	Optional	invisible

	(1) "invisible": the control is not visible without occupying any space.(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.(3) "cleared": the control is not visible but it still occupies		disabled cleared
straighttext	space. If the text of the control contains HTML tags then these are	Optional	true
	by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	1	false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
Binding			
method	Name of the event that is sent to the adapter when the user presses the button. If no method is specified, a default event is sent. If the method starts with javascript: the corresponding javascript method is called.	Optional	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:CHECKBOX

A responsive checkbox control.

Basic			
valueprop	Name of the adapter parameter that represents the control in the adapter.	Obligatory	
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid"		
1 1 1 1	"textid".	0 1 1	
helpid	Help id that is passed to the online help management in case the user presses F1 on the control.	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
Appearance			
displayonly	If set to true, the FIELD will not be accessible for input. It is just used as an output field.	Optional	true
			false
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying		disabled
	any space.		cleared
	(2) "disabled": the control is deactivated: it is "grayed"		
	and does not show any roll over effects any more.		
	(3)"cleared": the control is not visible but it still occupies space.		
styleclasses	CSS style classes separated by a blank.	Optional	form-control-sm
			form-control-lg
			font-italic
			font-weight-bold
			font-weight-bolder

			font-weight-light
			font-weight-lighter
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		
inline	Only set this property to true if you see rounding issues	Optional	true
	when zooming your page in Google Chrome or Edge Chromium browser. The property will force the browser to use a different rendering style for this itr. Use this property only if your ITR only contains the following controls: FIELD, LABEL, HDIST, ICON, BUTTON and/or XCIDATADEF and you are using pixel sizing.		false
straighttext	If the text of the control contains HTML tags then these	Optional	true
	are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.		false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying	Optional	true
	STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.		false

	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
renderasswitch	If set to "TRUE" the control is rendered as a switch.	Optional	true
			false
Binding			
valueprop	(already explained above)		
flush	Flushing behaviour of the input control.	Optional	screen
	By default an input into the control is registered within the browser client - and communicated to the server adapter object when a user e.g. presses a button. By using the FLUSH property you can change this behaviour. Setting FLUSH to "server" means that directly after changing the input a synchronization with the server adapter is triggered. As consequence you directly can react inside your adapter logic onto the change of the corresponding value Please be aware of that during the synchronization always all changed properties - also the ones that were changed before - are transferred to the adapter object, not only the one that triggered the synchonization. Setting FLUSH to "screen" means that the changed value		server
	is populated inside the page. You use this option if you have redundant usage of the same property inside one page and if you want to pass one changed value to all its representation directly after changing the value.		
flushmethod	When the data synchronization of the control is set to FLUSH="server" then you can specify an explicit event to be sent when the user updates the content of the control. By doing so you can distinguish on the server side from which control the flush of data was triggered.	Optional	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
statusprop	Name of the adapter parameter that dynamically passes information how the control should be rendered and how it should act. Valid parameter values at runtime:	Optional	

	"INVISIBLE", "FOCUS", "FOCUS_NO_SELECT", "ERROR", "ERROR_NO_FOCUS". In responsive controls additionally the values "WARNING" and "SUCCESS" are supported. The value "INVISIBLE" is only supported if the control does not support an INVISIBLEPROP. Use DISPLAYPROP or VISIBLEPROP if available to render the control displayonly/invisible/cleared.		
Natural			
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
njx:natsysvar	If the control shall be bound to a Natural system variable, this attribute specifies the name of the system variable.	Optional	
njx:natsysio	If the control shall be bound to a Natural system variable with the attribute njx:natsysvar, this attribute indicates if the system variable is modifiable. The default is false.		
njx:natcv	Name of a Natural control variable that shall be assigned to the control.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:COMBOFIX

The BMOBILE: COMBOFIX control allows specifying a defined set of values which can be selected. This set of values is defined as part of the layout definition - it cannot be controlled dynamically by the application. Use the BMOBILE: COMPOOPTION control to define the selection values. Optionally you can group the selection values by the control BMOBILE: COMBOGROUP.

Basic			
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
helpid	Help id that is passed to the online help management in case the user presses F1 on the control.	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
Appearance			
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled cleared
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		Cleareu
	(3)"cleared": the control is not visible but it still occupies space.		
combomode	Rendering mode of the control. "basic" is the default rendering style usually used in forms. "modern" has a slightly rendering style. Per default "basic" is used.	Optional	basic modern
datatype	By default, the control is managing its content as string.	Optional	date
	By explicitly setting a datatype you can define that the control will format the data coming from the server: if the		float
	field has datatype "date" and the user inputs "010304" then the input will be translated into "01.03.2004" (or other		int
	representation, dependent on date format settings).		long
	Please note: the datatype "float" is named a bit misleading - it represents any decimal format number. The server side		time
	representation may be a float value, but also can be a double or a BigDecimal property.		timestamp
	double of a bigDecimal property.		color
			xs:decimal

			xs:double
			xs:date
			xs:dateTime
			xs:time
			N n.n
			P n.n
			string n
			L
			xs:boolean
			xs:byte
			xs:short
styleclasses	CSS style classes separated by a blank.	Optional	form-control-sm
			form-control-lg
			custom-select-sm
			custom-select-lg
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering	_	
	of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating		
	them with a semicolon.		
	Sometimes it is useful to have a look into the generated		
	HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and		
size	select the "View source" or "View frame's source" function. Number of rows that are displayed inside the control. If	Optional	1
SIZE	specified as "1" (default) then the control is rendered as	Phonai	2
	combo box - if ">1" then the control is rendered as multi line selection.		_

			3
			int-value
title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML	Optional	true false
	text then STRAIGHTTEXT should be set to "true".		
placeholder	The text for the HTML placeholder attribute. The placeholder attribute specifies a short hint that describes the expected value.	Optional	
Binding			
valueprop	(already explained above)		
flush	Flushing behaviour of the input control.	Optional	screen
	By default an input into the control is registered within the browser client - and communicated to the server adapter object when a user e.g. presses a button. By using the FLUSH property you can change this behaviour. Setting FLUSH to "server" means that directly after changing the input a synchronization with the server adapter is triggered. As consequence you directly can react inside your adapter logic onto the change of the corresponding value Please be aware of that during the synchronization always all changed properties - also the ones that were changed before - are transferred to the adapter object, not only the one that triggered the synchonization. Setting FLUSH to "screen" means that the changed value is populated inside the page. You use this option if you have redundant usage of the same property inside one page and if you want to pass one changed value to all its representation directly after changing the value.		server
flushmethod	When the data synchronization of the control is set to FLUSH="server" then you can specify an explicit event to be sent when the user updates the content of the control.	Optional	

	By doing so you can distinguish on the server side from which control the flush of data was triggered.	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional
statusprop	Name of the adapter parameter that dynamically passes information how the control should be rendered and how it should act. Valid parameter values at runtime: "INVISIBLE", "FOCUS", "FOCUS_NO_SELECT", "ERROR", "ERROR_NO_FOCUS". In responsive controls additionally the values "WARNING" and "SUCCESS" are supported. The value "INVISIBLE" is only supported if the control does not support an INVISIBLEPROP. Use DISPLAYPROP or VISIBLEPROP if available to render the control displayonly/invisible/cleared.	Optional
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional
Natural		
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	
njx:natsysvar	If the control shall be bound to a Natural system variable, this attribute specifies the name of the system variable.	Optional
njx:natsysio	If the control shall be bound to a Natural system variable with the attribute njx:natsysvar, this attribute indicates if the system variable is modifiable. The default is false.	Optional
njx:natcv	Name of a Natural control variable that shall be assigned to the control.	Optional
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this	

	attributes to indicate for a generated statusprop variable to which field the statusprop belongs.		
Accessibility			
titleaslabel	If set to TRUE then an aria-label attribute is added with the title value. Default is FALSE	Optional	true false
Miscellaneous		'	
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:COMBOGROUP

See BMOBILE: COMBOFIX for the context of use of this control.

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	Sometimes obligatory	
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	

BMOBILE: COMBOOPTION

See BMOBILE: COMBOFIX for the context of use of this control.

Properties

Basic			
value	Actual value of the option that is passed into the adapter property specified by VALUEPROP inside the COMBOFIX control.	Obligatory	
name	Name that is displayed as selectable option. Either use the NAME property to specify the text in a "hard" way or use the TEXTID property to define the text in a language dependent way.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	Sometimes obligatory	
	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then	Optional	true false
	STRAIGHTTEXT should be set to "true".		
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	

BMOBILE:COMBODYN

The BMOBILE: COMBODYN control is the dynamic counterpart of the BMOBILE: COMBOFIX control. Whereas the selection options inside the BMOBILE: COMBOFIX control are defined in a fixed way inside the page definition, the BMOBILE: COMBODYN control offers the possibility to control the selection options dynamically in the application.

Adapter Interface

For a BMOBILE: COMBODYN with valueprop="selectedvalue" and validvaluesprop="theoptions" the following is generated:

- 1 SELECTEDVALUE (U) DYNAMIC 1 THEOPTIONS (1:*)
- 2 ID (U) DYNAMIC
- 2 NAME (U) DYNAMIC

Basic			
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
validvaluesprop	Name of the adapter parameter that provides the valid values that are available as selectable options.	Obligatory	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
Appearance			
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		cleared
	(3)"cleared": the control is not visible but it still occupies space.		
combomode	Rendering mode of the control. "basic" is the default rendering style usually used in forms. "modern" has a slightly rendering style. Per default "basic" is used.	Optional	basic modern
styleclasses	CSS style classes separated by a blank.	Optional	form-control-sm
			form-control-lg
			custom-select-sm
			custom-select-lg
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		

	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
size	Number of rows that are displayed inside the control. If specified as "1" (default) then the control is rendered as combo box - if ">1" then the control is rendered as multi line selection.	Optional	1 2 3 int-value
title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text		true false
helpid	then STRAIGHTTEXT should be set to "true". Help id that is passed to the online help management in	Optional	
placeholder	case the user presses F1 on the control. The text for the HTML placeholder attribute. The placeholder attribute specifies a short hint that describes the expected value.	Optional	
Binding			
valueprop	(already explained above)		
flush	Flushing behaviour of the input control.	Optional	screen
	By default an input into the control is registered within the browser client - and communicated to the server adapter object when a user e.g. presses a button. By using the FLUSH property you can change this behaviour.		server
	Setting FLUSH to "server" means that directly after changing the input a synchronization with the server adapter is triggered. As consequence you directly can react inside your adapter logic onto the change of the corresponding value Please be aware of that during the synchronization always all changed properties - also the ones that were changed before - are transferred to the		

	·	·
	adapter object, not only the one that triggered the synchonization.	
	Setting FLUSH to "screen" means that the changed value is populated inside the page. You use this option if you have redundant usage of the same property inside one page and if you want to pass one changed value to all its representation directly after changing the value.	
flushmethod	When the data synchronization of the control is set to FLUSH="server" then you can specify an explicit event to be sent when the user updates the content of the control. By doing so you can distinguish on the server side from which control the flush of data was triggered.	Optional
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional
statusprop	Name of the adapter parameter that dynamically passes information how the control should be rendered and how it should act. Valid parameter values at runtime: "INVISIBLE", "FOCUS", "FOCUS_NO_SELECT", "ERROR", "ERROR_NO_FOCUS". In responsive controls additionally the values "WARNING" and "SUCCESS" are supported. The value "INVISIBLE" is only supported if the control does not support an INVISIBLEPROP. Use DISPLAYPROP or VISIBLEPROP if available to render the control displayonly/invisible/cleared.	Optional
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional
Natural		
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	
njx:natsysvar	If the control shall be bound to a Natural system variable, this attribute specifies the name of the system variable.	Optional

njx:natsysio	If the control shall be bound to a Natural system variable with the attribute njx:natsysvar, this attribute indicates if the system variable is modifiable. The default is false.	Optional	
njx:natcv	Name of a Natural control variable that shall be assigned to the control.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.		
Accessibility		I	
titleaslabel	If set to TRUE then an aria-label attribute is added with the title value. Default is FALSE	Optional	true false
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:DATEINPUT2

A responsive form of the DATEINPUT2 control.

- Customizing Date and Calendar Formats
- Properties

Customizing Date and Calendar Formats

Default behavior for the date and calendar formats:

■ Date format in browser:

Per default the dates are shown in the browser according to the Natural DTFORM parameter.

■ Date format in Natural program:

Depending on the datatype property the Natural type D or an (A/U) DYNAMIC type is used. For the latter the format on the server is YYYYMMDD.

■ Calendar format:

The first day in week of the calendar is per default Sunday and can be customized per application and per single page at runtime by using the NJX:SESSIONPARAMS control

Some use cases require the formats to be customized independently of the central Natural format at design time and in a more flexible way. This is supported by the properties clientformat, severformat, and firstdayinweek. If these properties are set in a control, they will overwrite the

default behavior. For the clientformat and the serverformat property a subset of the Natural date edit masks is supported:

Character	Usage
DD	Day
ZD	Day with zero supression
MM	Month
ZM	Month with zero supression
YYYY	Year, 4 digits
YY	Year, 2 digits

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
datatype	By default, the DATEINPUT control is managing a day. By explicitly setting a datatype you can define that the control is managing a day and time. In the first use type CDATE within your adapter program - in the second case use type CTIMESTAMP.	Optional	date datetime xs:date xs:dateTime
serverformat	For alphanumeric datatypes you can choose the format of the date at design time. Examples: YYYY-MM-DD, DD.MM.YY, YY/MM/DD. A subset of the Natural date edit masks is supported. The serverforma is the format in which the data is sent to Natural.	Optional	YYYY-MM-DD DD/MM/YYYY MM-DD-YY
clientformat	You can choose the format of the date in the browser at design time. Examples: YYYY-MM-DD, DD.MM.YY, YY/MM/DD. A subset of the Natural date edit masks is supported. If set the Natural DTFORM parameter will not be used. This setting is only for the rendering in the client. It is independent of the set datatype.	Optional	YYYY-MM-DD DD/MM/YYYY MM-DD-YY
firstdayinweek	You can set the first day in week at design time. Valid values are SU - for Sunday - and MO - for		SU

	Monday. If set the value set by the NJX:SESSIONPARAMS control will not be used.		MO
helpid	Help id that is passed to the online help management in case the user presses F1 on the control.	Optional	
Binding			
valueprop	(already explained above)		
fromprop	Name of the adapter parameter that provides a lower limit for the value of the control. The value is used for client side validation of user input.	Optional	
toprop	Name of the adapter parameter that provides an upper limit for the value of the control. The value is used for client side validation of user input.	Optional	
statusprop	Name of the adapter parameter that dynamically passes information how the control should be rendered and how it should act. Valid parameter values at runtime: "INVISIBLE", "FOCUS", "FOCUS_NO_SELECT", "ERROR", "ERROR_NO_FOCUS". In responsive controls additionally the values "WARNING" and "SUCCESS" are supported. The value "INVISIBLE" is only supported if the control does not support an INVISIBLEPROP. Use DISPLAYPROP or VISIBLEPROP if available to render the control displayonly/invisible/cleared.		
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
flush	Flushing behaviour of the input control. By default an input into the control is registered within the browser client - and communicated to the server adapter object when a user e.g. presses a button. By using the FLUSH property you can change this behaviour. Setting FLUSH to "server" means that directly after changing the input a synchronization with the server adapter is triggered. As consequence you directly can react inside your adapter logic onto the change of the corresponding value Please be aware of that during the synchronization always all changed properties - also the ones that were changed before - are		screen

flushmethod	transferred to the adapter object, not only the one that triggered the synchonization. Setting FLUSH to "screen" means that the changed value is populated inside the page. You use this option if you have redundant usage of the same property inside one page and if you want to pass one changed value to all its representation directly after changing the value. When the data synchronization of the control is set to FLUSH="server" then you can specify an explicit event to be sent when the user updates	Optional	
	the content of the control. By doing so you can distinguish on the server side from which control the flush of data was triggered.		
holidaysurlprop	Name of the Adapter paramter which provides the URL for a json file with custom holidays dynamically at runtime.	Optional	
Appearance			
displayonly	If set to true, the FIELD will not be accessible for input. It is just used as an output field.	Optional	true false
styleclasses	CSS style classes separated by a blank.	Optional	form-control-sm form-control-lg font-italic font-weight-bold font-weight-bolder font-weight-light font-weight-light
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon.	Optional	

	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
numberofmonths	Number of months shown for selection. Default is 1	Optional	
popuponalt40	Value help in a field is triggered either by clicking with the mouse or by pressing a certain key inside the field. The "traditional" keys are "cusrsor-down", "F7" or "F4". Sometimes you do not want to mix other "cursor-down" behaviour (e.g. scrolling in lists) with the value help behaviour. In this case switch this property to "true" - and the value help will only come up anymore when "alt-cursor-down" is pressed.	Optional	true
popuponF4F7	Per default the calendar is opened on F4 and F7. Set this property to false if you want to use F4 or F7 for other purpose.	Optional	true false
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
popupicon	URL of image that is displayed inside the right corner of the field to indicate to the user that there is some value help available Any image type (.gif, .jpg,) that your browser does understand is valid. Use the following options to specify the URL: (A) Define the URL relative to your page. Your page is generated directly into your project's folder. Specifying "images/xyz.gif" will point into a directory parallel to your page. Specifying "/HTMLBasedGUI/images/new.gif" will point to an image of a neighbour project.		gif jpg jpeg

	(B) Define a complete URL, like "http://www.softwareag.com/images/logo.gif".		
placeholder	The text for the HTML placeholder attribute. The placeholder attribute specifies a short hint that describes the expected value.	Optional	
holidaysurl	URL for json file, which contains custom holidays.	Optional	
holidaysstyleclass	Name of the css style class, which is used for the rendering of custom holidays. Default is DATEINPUT2Holidays	Optional	
holidaysdescriptionastooltip	Set this property to true if you want to show descriptions in the json file as tool tips.	Optional	true false
Natural			
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2. If the control shall be bound to a Natural system		
iyx.iiatsysvai	variable, this attribute specifies the name of the system variable.	Optional	
njx:natsysio	If the control shall be bound to a Natural system variable with the attribute njx:natsysvar, this attribute indicates if the system variable is modifiable. The default is false.	Optional	
njx:natcv	Name of a Natural control variable that shall be assigned to the control.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes		

	to indicate for a generated statusprop variable to which field the statusprop belongs.		
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:DROPDOWN

The control BMOBILE: DROPDOWN renders a dropdown button. Add the dropdown content, i.e. the content you want to show, when the button is clicked, as sub controls of the BMOBILE: DROPDOWN. Use the BMOBILE: DROPDOWNITEM to render leight-weight dropdown menus. You can also add a BMOBILE: FORM as dropdown content. This can be used for instance to implement a multiselect dropdown with BMOBILE: CHECKBOX controls. Examples are available in the *NaturalAjaxDemos*. Use the BMOBILE: DROPDOWNHEADER and the BMOBILE: DROPDOWNSEPARATOR to apply structure to your dropdown content. Use the BMOBILE: DROPDOWNLIST to apply drop down items dynamically from your Natural program at runtime.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Sometimes obligatory	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".		
Appearance			
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that	Optional	true false

	the browser will directly render the characters without HTML interpretation.		
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
styleclasses	CSS style classes separated by a blank.	Optional	ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
dropdownmode	Set this if you want to expand the menu upwards or if you want to position the menu to the right	Optional	dropdown
	or to the left. Supported values are dropdown,		dropright

	dropup, dropleft, dropright. The default is dropdown.		dropleft dropup	
buttonclasses	CSS style classes separated by a blank for rendering the dropdown button in the control.	Optional	btn-default btn-primary btn-info btn-success btn-warning btn-danger btn-sm btn-lg btn-icon-sm btn-icon-lg btn-responsive btn-outline-primary btn-outline-info btn-outline-warning btn-outline-danger close mx-auto	
buttonstyle	CSS style definition for rendering the dropdown button in control.	Optional		
renderasicon	Set to TRUE if you specified an icon font without any text. This will render the button like an icon. The margin and padding is reduced and the font-size is adapted.	Optional	true false	
menuclasses	CSS style classes separated by a blank for rendering the dropdown menu.	Optional	dropdown-menu-right dropdown-menu-sm-right dropdown-menu-md-right dropdown-menu-lg-right	

			dropdown-menu-left
			dropdown-menu-sm-left
			dropdown-menu-md-left
			dropdown-menu-lg-left
Binding		I	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:DROPDOWNLIST

See BMOBILE: DROPDOWN (above) for the context of use of this control.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
styleclasses	CSS style classes separated by a blank.		bg-light ml-* mr-* mx-* mx-sm-* mx-md-* mx-lg-*

			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Natural		l	
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be		

	#GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	_	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.		

BMOBILE:DROPDOWNHEADER

See BMOBILE: DROPDOWN for the context of use of this control.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Sometimes obligatory	
Appearance			
styleclasses	CSS style classes separated by a blank.	Optional	d-none d-md-block
			d-none d-lg-block
			text-uppercase
			font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		

	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	•	true false
Binding	-	l.	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	

BMOBILE:DROPDOWNITEM

See BMOBILE: DROPDOWN for the context of use of this control.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Sometimes obligatory	
helpid	Help id that is passed to the online help management in case the user presses F1 on the control.	Optional	
Appearance			
styleclasses	CSS style classes separated by a blank.	Optional	font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light

			font-weight-lighter
			text-lowercase
			text-uppercase
			text-danger
			text-info
			text-primary
			text-secondary
			text-success
			text-warning
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
straighttext	If the text of the control contains HTML tags then these	Optional	true
	are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.		false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
Binding			
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
inactiveprop	Name of the adapter parameter that dynamically passes information if the item should be inactive.	Optional	
method	Name of the event that is sent to the adapter when clicking on the control.	Optional	
	I .	l	

BMOBILE:DROPDOWNSEPARATOR

See BMOBILE: DROPDOWN for the context of use of this control.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
Appearance		J.	
styleclasses	CSS style classes separated by a blank.	Optional	mt-1
			mt-2
			mt-3
			mt-4
			mt-5
			mt-sm-*
			mt-md-*
			mt-lg-*
			mt-xl-*
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

BMOBILE:FFIELD

A responsive form of the FIELD control.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
password	If set to "true", each entered character is displayed as a '*'.	Optional	true false
helpid	Help id that is passed to the online help management in case the user presses F1 on the control.	Optional	
Appearance	,	ļ.	
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
styleclasses	CSS style classes separated by a blank.	Optional	form-control-sm form-control-lg font-italic font-weight-bold font-weight-bolder

			font-weight-light
			font-weight-lighter
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your	Optional	
placeholder	browser and select the "View source" or "View frame's source" function. The text for the HTML placeholder attribute. The placeholder attribute	Optional	
	specifies a short hint that describes the expected value.		
maxlength	Maximum number of characters that a user may enter. This property is not depending on the LENGTH property - please do not get confused by the similar naming. MAXLENGTH has nothing to do with the optical sizing of the control but	Optional	5 10 15 20
	only with the number of characters you may input.		int-value
autotab	If set to true, an automatic tab is executed for fields with a specified MAXLENGTH when the maxlength value is reached. For fields without a MAXLENGTH specified it has no effect. Default is true.	Optional	true false
uppercase	If "true" then all input is automatically transferred to upper case characters.	Optional	true false

shownull	If set to FALSE numeric field are shown as empty if the value is 0 or 0.0	Optional	true
	as empty if the value is 0 of 0.0		false
formautocomplete	This property only has effects if the withformtag property in the PAGEBODY	Optional	true
	is activated. In this case you can switch on and off the browser's autocomplete behavior for HTML form tags in single FIELD controls. Default is TRUE.		false
email	If set to true E-Mail validation is done by the browser.	Optional	true
displayonly	If set to true, the FIELD will not be accessible for input. It is just used as an output field.	Optional	true false
invisiblemode	If the visibility of the control is determined	Optional	invisible
	dynamically by an adapter property then there are two rendering modes if the		disabled
	visibility is "false":		cleared
	(1) "invisible": the control is not visible.(2) "cleared": the control is not visible but it still occupies space.		
datatype	By default, the FIELD control is managing its content as string. By explicitly setting	Optional	date
	a datatype you can define that the control		float
	will check the user input if it reflects the datatype. E.g. if the user inputs "abc" into		long
	a field with datatype "int" then a corresponding error message will popup		time
	when the user leaves the field.		timestamp
	will format the data coming from the server or coming form the user input: if		color
	the field has datatype "date" and the user inputs "010304" then the input will be		xs:decimal
	translated into "01.03.2004" (or other representation, dependent on date format		xs:double
	settings).		xs:date
	In addition valeu popups are offered for		xs:dateTime
	the user automatically for some datatypes: e.g. when specifying datatype "date" the		xs:time

	automatically the field provides a calendar input popup.		N n.n
	Please note: the datatype "float" is named		P n.n
	a bit misleading - it represents any		string n
	decimal format number. The server side representation may be a float value, but		L
	also can be a double or a BigDecimal property.		xs:boolean
	r - r - y		xs:byte
			xs:short
editmask	NATPAGE only: A subset of the Natural edit masks is supported depending on the data type.	Optional	
required	If set to true a value is required.	Optional	true
			false
validation	The HTML validation attribute for input controls.	Optional	[a-zA-Z0-9]
	COLUTIOIS.		{1,}\\@[a-zA-Z0-9]
			$\{1,\}\setminus\setminus\setminus w\{2,\}\setminus d\{5\}$
			[0-9)(-/+]+
validationmessage	The message which is shown when the validation is not successful.	Optional	
validationmessagetextid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
	Do not specify a "name" inside the control if specifying a "textid".		
withtogglepassword	If set to TRUE a small toggle button is shown which allows to show the	Optional	true
	password in clear text and hide it again.		false
Binding			
hotkeys	Semicolon separated list of hot keys. A hotkey consists of a list of keys and a method name. Separate the keys by "-" and the method name again with a semicolon	Optional	
	Example:		

	ctrl-alt-65;onCtrlAltA;13;onEnterdefines two hot keys. Method onCtrlAltA is invoked if the user presses Ctrl-Alt-A. Method "onEnter" is called if the user presses the ENTER key. Use the popup help within the Layout		
	Painter to input hot keys.		
alwaysflush	If set to TRUE then a specified server flushmethod is also called in case the value has not changed. The default is FALSE, meaning that a server flushmethod is only called for a changed value.	Optional	true false
flush	Flushing behaviour of the input control.	Optional	screen
	By default an input into the control is registered within the browser client - and communicated to the server adapter object when a user e.g. presses a button. By using the FLUSH property you can change this behaviour.		server
	Setting FLUSH to "server" means that directly after changing the input a synchronization with the server adapter is triggered. As consequence you directly can react inside your adapter logic onto the change of the corresponding value Please be aware of that during the synchronization always all changed properties - also the ones that were changed before - are transferred to the adapter object, not only the one that triggered the synchonization.		
	Setting FLUSH to "screen" means that the changed value is populated inside the page. You use this option if you have redundant usage of the same property inside one page and if you want to pass one changed value to all its representation directly after changing the value.		
flushmethod	When the data synchronization of the control is set to FLUSH="server" then you can specify an explicit event to be sent when the user updates the content of the control. By doing so you can distinguish	Optional	

	on the server side from which control the flush of data was triggered.	
flushindexprop	Name of a changeindexprop property of another control. On flush='screen" the value of the specified property is automatically increased so that the controls is automatically refreshed. This property is ignored for flush="server"	Optional
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional
statusprop	Name of the adapter parameter that dynamically passes information how the control should be rendered and how it should act. Valid parameter values at runtime: "INVISIBLE", "FOCUS", "FOCUS_NO_SELECT", "ERROR", "ERROR_NO_FOCUS". In responsive controls additionally the values "WARNING" and "SUCCESS" are supported. The value "INVISIBLE" is only supported if the control does not support an INVISIBLEPROP. Use DISPLAYPROP or VISIBLEPROP if available to render the control displayonly/invisible/cleared.	Optional
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional
Add-ons		
autocompleteref	Adds autocomplete functionality to the FIELD control. As value set the id of the AUTOCOMPLETE control.	Optional
autocompletedisplayname	Name of the value to be displayed in an additional control.	Optional
autocompletedisplayref	Sets a reference to an additional control to display additional information on selection. As value set the value prop of the control in which you would like to display the information.	Optional
autocompleteresultsref	Sets a reference to an additional control to display the total number of results. Use this when the number of matching items can be very high and you limited the	Optional

autocompletewithdropdown	number of displayed items in the dropdown for performance reasons. As value set the valueprop of the control in which you would like to display the total number. If set to "TRUE" a dropdown button/icon will be appended to the field. When it is clicked, all items are shown.	Optional	true false
Natural			
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1.	Optional	
njx:natsysvar	If the control shall be bound to a Natural system variable, this attribute specifies the name of the system variable.	Optional	
njx:natsysio	If the control shall be bound to a Natural system variable with the attribute njx:natsysvar, this attribute indicates if the system variable is modifiable. The default is false.	Optional	
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcv	Name of a Natural control variable that shall be assigned to the control.	Optional	

njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	
	neid the statusprop beforegs.		
Accessibility			
titleaslabel	If set to TRUE then an aria-label attribute	Optional	true
	is added with the title value. Default is FALSE		false
Miscellaneous			1
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:FLABEL

A responsive form of the LABEL control.

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Sometimes obligatory	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	Sometimes obligatory	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
Appearance			
invisiblemode	If the visibility of the control is determined dynamically by an adapter property then there are two rendering modes if the visibility is "false": (1) "invisible": the control is not visible.	Optional	invisible cleared

	(2)"cleared": the control is not visible but it still occupies space.		
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
styleclasses	CSS style classes separated by a blank.	Optional	col-* col-sm-* col-sm-* col-md-* col-lg-* col-xl-* form-control-sm form-control-lg font-italic font-weight-bold font-weight-bolder font-weight-light font-weight-lighter text-info sr-only text-primary text-secondary text-success text-warning

style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
Binding			
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
Miscellaneous			1
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:FTEXTAREA

A responsive form of the TEXTAREA control.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
rows	Height of control specified by number of rows. Either define the height by the HEIGHT property or by the ROWS property. Do not specify both! When specifying the height by ROWS then be aware of that the height depends from the font size used inside the control (that is defined in the styles sheet definition).	Optional	1 2 3 int-value
cols	Width of control specified by number of characters. Either define the width by the WIDTH property or by the COLS property. Do not specify both! When specifying the width by COLS then be aware of that the width depends from the font size used inside the control (that is defined in the styles sheet definition).	Optional	1 2 3 int-value
styleclasses	CSS style classes separated by a blank.	Optional	col-* col-sm-* col-sm-* col-md-* col-lg-* col-xl-* form-control-sm form-control-lg font-italic font-weight-bold font-weight-bolde

			text-info
			sr-only
			text-primary
			text-secondary
			text-success
			text-warning
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
placeholder	The text for the HTML placeholder attribute. The placeholder attribute specifies a short hint that describes the expected value.	Optional	
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled cleared
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		cicurcu
	(3)"cleared": the control is not visible but it still occupies space.		

title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
helpid	Help id that is passed to the online help management in case the user presses F1 on the control.	Optional	
maxlength	Maximum number of characters that a user may enter. This property is not depending on the LENGTH property - please do not get confused by the similar naming. MAXLENGTH has nothing to do with the optical sizing	Optional	5 10 15
	of the control but only with the number of characters you may input.		20 int-value
displayonly	If set to true, the FIELD will not be accessible for input. It is just used as an output field.	Optional	true false
hotkeys	Semicolon separated list of hot keys. A hotkey consists of a list of keys and a method name. Separate the keys by "-" and the method name again with a semicolon Example: ctrl-alt-65;onCtrlAltA;13;onEnterdefines two hot keys. Method onCtrlAltA is invoked if the user presses Ctrl-Alt-A. Method "onEnter" is called if the user presses the ENTER key. Use the popup help within the Layout Painter to input hot keys.		
required	If set to true a value is required.	Optional	true
l			false

wrap	Specifies the line wrapping inside the control. By default a line that exceeds the width of the control is broken automatically.	Optional
	You may define this property to not wrap at all ("off") - in this case the text control offers horizontal scroll bars to scroll the text.	
	There are two styles of wrapping "soft" and "hard". The difference between "soft" and "hard" is the way the text is - if changed by the user - passed back to the adapter property: when specifying "soft" then line breaks which are caused by wrapping are not sent to the server, when specifying "hard" then line breaks caused by wrapping are sent as carriage return/ line feed Be carefule when specifying "hard" as consequence!	
	The wrap attribute is not part of the HTML standard. It depends on the browser if wrap=hard/soft are supported.	
Natural		
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	
njx:natsysvar	If the control shall be bound to a Natural system variable, this attribute specifies the name of the system variable.	Optional
njx:natsysio	If the control shall be bound to a Natural system variable with the attribute njx:natsysvar, this attribute indicates if the system variable is modifiable. The default is false.	Optional
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	
njx:natcv	Name of a Natural control variable that shall be assigned to the control.	Optional
		•

njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	
Accessibility			
titleaslabel	If set to TRUE then an aria-label attribute is added with the title value. Default is FALSE	Optional	true false
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:FTEXTOUT

Supports plain read-only text in forms.

Basic		
valueprop	Name of the adapter parameter that provides the content of the control.	7
datatype	By default, the FIELD control is managing its content as Optional	date
	string. By explicitly setting a datatype you can define that the control	float
	will check the user input if it reflects the datatype. E.g.	int
	if the user inputs "abc" into a field with datatype "int" then a corresponding error message will popup when	long
	the user leaves the field.	time
	will format the data coming from the server or coming form the user input: if the field has datatype "date" and	timestamp
	the user inputs "010304" then the input will be translated	color
	into "01.03.2004" (or other representation, dependent on date format settings).	xs:decimal
	In addition valeu popups are offered for the user	xs:double
	automatically for some datatypes: e.g. when specifying datatype "date" the automatically the field provides a	xs:date
	calendar input popup.	xs:dateTime

	Please note: the datatype "float" is named a bit misleading - it represents any decimal format number. The server side representation may be a float value, but also can be a double or a BigDecimal property.		xs:time N n.n P n.n string n L xs:boolean xs:byte xs:short
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
invisiblemode	This property has three possible values: (1) "invisible": the control is not visible without occupying any space. (2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more. (3) "cleared": the control is not visible but it still occupies space.	Optional	invisible cleared
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false

	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
styleclasses	CSS style classes separated by a blank.	Optional	col-*
			col-sm-*
			col-md-*
			col-lg-*
			col-xl-*
			form-control-sm
			form-control-lg
			font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
			text-info
			sr-only
			text-primary
			text-secondary
			text-success
			text-warning
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style		

	definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Natural			
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
njx:natsysvar	If the control shall be bound to a Natural system variable, this attribute specifies the name of the system variable.	Optional	
njx:natsysio	If the control shall be bound to a Natural system variable with the attribute njx:natsysvar, this attribute indicates if the system variable is modifiable. The default is false.	Optional	
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcv	Name of a Natural control variable that shall be assigned to the control.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	
Accessibility			
titleaslabel	If set to TRUE then an aria-label attribute is added with the title value. Default is FALSE	Optional	true false
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	_	

BMOBILE:GOOGLEMAP

A responsive Google map control.

Basic			
apikeypagename	Name of the Maps API Key page. Example: mygooglemapsapikey.html. Keep this file within the project directory (directory within the CIS HTML pages are kept). The GOOGLEMAP-control expects this file within certain Javascript includes and content. Have look into chapter "Google Map - Before You Start" within the Developers Guide	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
Appearance			
mapmode	Lets you toggle between map types (e.g., Map and Satellite)	Optional	2
controltype	Lets you toggle between a small and large pan/zoom control	Optional	small large

BMOBILE:ICON

A responsive form of the ICON control.

Basic			
iconurl	URL of image that is displayed inside the control. Any image type (.gif, .jpg,) that your browser does understand is valid.	Optional	
	Use the following options to specify the URL:		
	(A) Define the URL relative to your page. Your page is generated directly into your project's folder. Specifiying "images/xyz.gif" will point into a directory parallel to your page. Specifying "/HTMLBasedGUI/images/new.gif" will point to an image of a neighbour project.		
	(B) Define a complete URL, like "http://www.softwareag.com/images/logo.gif".		
iconurlprop	Name of adapter parameter that provides as value the URL of the image that is shown inside the control.	Optional	
method	Name of the event that is sent to the adapter when clicking on the control.	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		cleared
	(3)"cleared": the control is not visible but it still occupies space.		
title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		

		,	
titletextid	Text ID that is passed to the multi lanaguage management - representing the tooltip text that is used for the control.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.		true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
styleclasses	CSS style classes separated by a blank.	Optional	baricon
			baricon-svg
			icon-svg-primary
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
helpid	Help id that is passed to the online help management in case the user presses F1 on the control.	Optional	
Natural			1
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2		

	respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	_	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	•	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	•	

BMOBILE:IMAGEOUT

A responsive image control.

Basic			
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
width	Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.	Optional	100 120 140 160

	(B) Pixel sizing: just input a number value (e.g. "100").		180
	(C) Percentage sizing: input a percantage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct results if the parent element of the control properly defines		200 50%
	a width this control can reference. If you specify this control to have a width of 50% then the parent element (e.g. an ITR-row) may itself define a width of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		100%
height	Height of the control.	Optional	100
	There are three possibilities to define the height:		150
	(A) You do not define a height at all. As consequence the control will be rendered with its default height. If the control		200
	is a container control (containing) other controls then the		250
	height of the control will follow the height of its content.		300
	(B) Pixel sizing: just input a number value (e.g. "20").		250
	(C) Percentage sizing: input a percentage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct		400
	results if the parent element of the control properly defines a height this control can reference. If you specify this control		50%
	to have a height of 50% then the parent element (e.g. an		100%
	ITR-row) may itself define a height of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	img-circle
			img-rounded
			img-thumbnail
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		

I	Sometimes it is useful to have a look into the generated		
	HTML code in order to know where direct style definitions		
	are applied. Press right mouse-button in your browser and		
s	select the "View source" or "View frame's source" function.		
Natural			
1 '	f a Natural variable with a name not valid for Application	Optional	
I I	Designer (for instance #FIELD1) shall be bound to the control,		
	different name (for instance HFIELD1) can be bound		
i:	nstead. If the original name (in this case #FIELD1) is then		
s	specified in this attribute, the original name is generated into		
t	he parameter data area of the Natural adapter and a		
n	mapping between the two names is generated into the		
F	PROCESS PAGE statement of the Natural adapter. This		
n	mapping must not break a once defined group structure. If		
f	or instance a grid control that is bound to a name of GRID1		
c	contains fields that are bound to FIELD1 and FIELD2		
r	respectively, the corresponding njx:natname values may be		
#	GRID1.#FIELD1 and #GRID1.#FIELD2, but not		
#	GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
njx:natstringtype I	f the control shall be bound to a Natural system variable of	Optional	
s	string format with the attribute njx:natsysvar, this attribute		
ii	ndicates the format of the string, A (code page) or U		
(Unicode). The default is A.		
njx:natcomment T	The value of this attribute is generated as comment line into	Optional	
t	he parameter data area of the Natural adapter, before the		
f	ield name. The Map Converter, for instance, uses this		
a	attributes to indicate for a generated statusprop variable to		
v	which field the statusprop belongs.		
Miscellaneous		1	
testtoolid U	Jse this attribute to assign a fixed control identifier that can	Optional	
b	be later on used within your test tool in order to do the object		
i	dentification		

BMOBILE:RADIOBUTTON

A responsive radio button control.

Basic			
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
value	Value that represents this instance of the RADIOBUTTON control.	Optional	
	The value is set into the adapter property that is defined by the VALUEPROP property when the user clicks onto the control Vice versa: the control is switched to "marked" when the adapter property holds the value defined.		
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
helpid	Help id that is passed to the online help management in case the user presses F1 on the control.	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
Appearance			
styleclasses	CSS style classes separated by a blank.	Optional	form-control-sm form-control-lg
			font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		

	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
inline	Only set this property to true if you see rounding issues when zooming your page in Google Chrome or Edge Chromium browser. The property will force the browser to use a different rendering style for this itr. Use this property only if your ITR only contains the following controls: FIELD, LABEL, HDIST, ICON, BUTTON and/or XCIDATADEF and you are using pixel sizing.	•	true false
displayonly	If set to true, the FIELD will not be accessible for input. It is just used as an output field.	Optional	true false
invisiblemode	This property has three possible values: (1) "invisible": the control is not visible without occupying any space. (2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more. (3) "cleared": the control is not visible but it still occupies space.	Optional	invisible disabled cleared
datatype	By default, the control is managing its content as string. By explicitly setting a datatype you can define that the control will format the data coming from the server: if the field has datatype "date" and the user inputs "010304" then the input will be translated into "01.03.2004" (or other representation, dependent on date format settings). Please note: the datatype "float" is named a bit misleading - it represents any decimal format number. The server side representation may be a float value, but also can be a double or a BigDecimal property.		xs:string N n.n P n.n string n
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false

	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
Binding			
valueprop	(already explained above)		
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
statusprop	Name of the adapter parameter that dynamically passes information how the control should be rendered and how it should act. Valid parameter values at runtime: "INVISIBLE", "FOCUS", "FOCUS_NO_SELECT", "ERROR", "ERROR_NO_FOCUS". In responsive controls additionally the values "WARNING" and "SUCCESS" are supported. The value "INVISIBLE" is only supported if the control does not support an INVISIBLEPROP. Use DISPLAYPROP or VISIBLEPROP if available to render the control displayonly/invisible/cleared.		
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
flush	Flushing behaviour of the input control. By default an input into the control is registered within the browser client - and communicated to the server adapter object when a user e.g. presses a button. By using the FLUSH property you can change this behaviour. Setting FLUSH to "server" means that directly after changing the input a synchronization with the server adapter is triggered. As consequence you directly can react inside your adapter logic onto the change of the corresponding value Please be aware of that during the synchronization always all changed properties - also the ones that were changed before - are transferred to the adapter object, not only the one that triggered the synchonization.		screen

flushmethod	Setting FLUSH to "screen" means that the changed value is populated inside the page. You use this option if you have redundant usage of the same property inside one page and if you want to pass one changed value to all its representation directly after changing the value. When the data synchronization of the control is set to FLUSH="server" then you can specify an explicit event to be sent when the user updates the content of the control. By doing so you can distinguish on the server	
	side from which control the flush of data was triggered.	
Natural		1
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	
Miscellaneous		
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional

BMOBILE:TOGGLER

A toggle button you can use in bars to toggle the visibility of containers like the BMOBILE: SIDEBAR.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
toggleref	The value of the toggleid property of the control for which visibility should be toggled.	Optional	
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
styleclasses	CSS style classes separated by a blank.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

6 Responsive Containers

 BMOBILE:CONTAINER BMOBILE:FORM, BMOBILE:FORMINLINE BMOBILE:FORMAREA BMOBILE:FORMGROUP BMOBILE:LISTGROUP BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and 		
 BMOBILE:COL BMOBILE:PANEL BMOBILE:ROW BMOBILE:CONTAINER BMOBILE:FORM, BMOBILE:FORMINLINE BMOBILE:FORMAREA BMOBILE:FORMGROUP BMOBILE:LISTGROUP BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and 	■ BMOBILE:CARD	100
 BMOBILE:PANEL BMOBILE:ROW BMOBILE:CONTAINER BMOBILE:FORM, BMOBILE:FORMINLINE BMOBILE:FORMAREA BMOBILE:FORMGROUP BMOBILE:LISTGROUP BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and 	■ BMOBILE:CARDCONTAINER	109
 BMOBILE:ROW BMOBILE:CONTAINER BMOBILE:FORM, BMOBILE:FORMINLINE BMOBILE:FORMAREA BMOBILE:FORMGROUP BMOBILE:LISTGROUP BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and 	■ BMOBILE:COL	111
 BMOBILE:CONTAINER BMOBILE:FORM, BMOBILE:FORMINLINE BMOBILE:FORMAREA BMOBILE:FORMGROUP BMOBILE:LISTGROUP BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and 	■ BMOBILE:PANEL	112
 BMOBILE:FORM, BMOBILE:FORMINLINE BMOBILE:FORMAREA BMOBILE:FORMGROUP BMOBILE:LISTGROUP BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and 	■ BMOBILE:ROW	114
 BMOBILE:FORMAREA BMOBILE:FORMGROUP BMOBILE:LISTGROUP BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and 	■ BMOBILE:CONTAINER	115
 BMOBILE:FORMGROUP BMOBILE:LISTGROUP BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and 	■ BMOBILE:FORM, BMOBILE:FORMINLINE	117
 BMOBILE:LISTGROUP BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and 		
 BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZONT-ALBAR, BMOBILE:CONTENT	■ BMOBILE:FORMGROUP	121
ALBAR, BMOBILE:CONTENT	■ BMOBILE:LISTGROUP	123
 BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB	■ BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDEBARGROUP, BMOBILE:HORIZON	NT-
■ BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and	ALBAR, BMOBILE:CONTENT	126
	■ BMOBILE:TABPANE, BMOBILE:VERTICALTABPANE and BMOBILE:TAB	131
BMOBILE:PAGER 13	■ BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and	
	BMOBILE:PAGER	138

BMOBILE:CARD

- BMOBILE:CARDBODY
- BMOBILE:CARDFOOTER
- BMOBILE:CARDHEADER

A card is a box with an optional header, an optional footer, an optional image, and a body with textual content, a list group, or both.

You can arrange multiple cards in a **BMOBILE:CARDCONTAINER**. You can also add them to other controls into a **BMOBILE:ROW**.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
imageurl	URL of image that is displayed inside the control. Any image type (.gif, .jpg,) that your browser does understand is valid.	Optional	
	Use the following options to specify the URL:		
	(A) Define the URL relative to your page. Your page is generated directly into your project's folder. Specifiying "images/xyz.gif" will point into a directory parallel to your page. Specifying "/HTMLBasedGUI/images/new.gif" will point to an image of a neighbour project.		
	(B) Define a complete URL, like "http://www.softwareag.com/images/logo.gif".		
imageurlprop	Name of adapter parameter that provides as value the URL of the image that is shown inside the control.	Optional	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
Appearance			
invisiblemode	If the visibility of the control is determined dynamically by an adapter property then there are two rendering modes if	_	
	the visibility is "false":		disabled
	(1) "invisible": the control is not visible.		cleared
	(2)"cleared": the control is not visible but it still occupies space.		
styleclasses	CSS style classes separated by a blank.	Optional	bg-light

			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
imagestyleclasses	CSS style classes separated by a blank.	Optional	img-circle
			img-rounded

			img-thumbnail
imagestyle	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:	Optional	
	border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
imageposition	The position of the image within it's container. Valid values are "top" and "bottom".	Optional	top bottom left right
imageoverlay	If set to TRUE the image will be used as card background and overlayed with the card body.	Optional	true false
tabindex	Index that defines the tab order of the control. Controls are selected in increasing index order and in source order to resolve duplicates.	Optional	-1 0 1 2 5 10 32767

BMOBILE:CARDBODY

A cardbody renders contextual content in a card.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
subname	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
text	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
subnameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.		
textprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.		
Appearance			
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*

			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
namestyleclasses	CSS style classes separated by a blank.	Optional	font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
			text-lowercase
			text-uppercase
			text-danger
			text-info
			text-primary
			text-secondary
			text-success
			text-warning

namestyle	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
subnamestyleclasses	CSS style classes separated by a blank.	Optional	font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
			text-lowercase
			text-uppercase
			text-danger
			text-info
			text-primary
			text-secondary
			text-success
			text-warning
subnamestyle	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		

	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
textstyleclasses	CSS style classes separated by a blank.	Optional	font-italic
			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
			text-lowercase
			text-uppercase
			text-danger
			text-info
			text-primary
			text-secondary
			text-success
			text-warning
textstyle	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right		

mouse-button in your browser and select the	
"View source" or "View frame's source" function.	

BMOBILE:CARDFOOTER

An optional footer for cards.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	Optional	
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
Appearance			I
styleclasses	CSS style classes separated by a blank.	Optional	d-none d-md-block d-none d-lg-block text-uppercase font-italic
			font-weight-bold font-weight-bolder font-weight-light font-weight-lighter
style	CSS style definition that is directly passed into this control.	Optional	

With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
border: 1px solid #FF0000		
background-color: #808080		
You can combine expressions by appending and separating them with a semicolon.		
Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

BMOBILE:CARDHEADER

An optional header for cards.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	Optional	
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
Appearance			1
styleclasses	CSS style classes separated by a blank.	Optional	d-none d-md-block
			d-none d-lg-block
			text-uppercase
			font-italic

			font-weight-bold
			font-weight-bolder
			font-weight-light
			font-weight-lighter
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

BMOBILE:CARDCONTAINER

A BMOBILE:CARDCONTAINER contains several cards. The following options are supported to arrange the cards in the container:

Card Decks

The cards are rendered as a grid of cards with equal height and width. On small devices the cards are arranged vertically. On medium and large devices, cards are arranged horizontally in one line.

Card Groups

The arrangement of the cards is the same as for card decks. The only difference is that there are no gaps between the cards.

Card Columns

You can create masonry-like grid of cards. The cards can be of different sizes. Simply add several cards to the container, and they will be arranged – including line breaks – automatically depending on the number of cards and the device.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled cleared
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.(3) "cleared": the control is not visible but it still occupies		
A	space.		
Appearance styleclasses	CSS style classes separated by a blank.	Optional	bg-light
,	and any second separation by the same in	- F 1.5.1.1.	ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	

With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
border: 1px solid #FF0000		
background-color: #808080		
You can combine expressions by appending and separating them with a semicolon.		
Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

BMOBILE:COL

BMOBILE: COL supports the responsive **grid system of Bootstrap**.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.(3) "cleared": the control is not visible but it still occupies space.		cleared
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.		
styleclasses	CSS style classes separated by a blank.	Optional	col-auto
			col
			col-*
			col-sm-*
			col-md-*

			col-lg-*
			col-xl-*
			offset-*
			offset-sm-*
			offset-md-*
			offset-lg-*
			offset-xl-*
			mx-auto
			btn-group
			btn-group-vertical
style	CSS style definition that is directly passed into this control.	Optional	
		1	
	With the style you can individually influence the rendering		
	of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are		
	applied. Press right mouse-button in your browser and select		
	the "View source" or "View frame's source" function.		

BMOBILE:PANEL

BMOBILE:PANEL supports the responsive grid system of Bootstrap.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
foldable	The "folding"-function that is available by clicking on the title of the area can be switched off ("false"). "True" is the default.	Optional	true false
foldedprop	Name of adapter parameter which controls whether the content of the ROWAREA is folded (true) or displayed (false). By using this property you can dynamically control the "folded"-status of the control at runtime.	Optional	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
tabindex	Index that defines the tab order of the control. Controls are selected in increasing index order and in source order to resolve duplicates.	Optional	-1 0
			1
			2
			5
			10
			32767
Appearance			l.
invisiblemode	If the visibility of the control is determined dynamically by an adapter property then there are two rendering modes if the	Optional	invisible
	visibility is "false":		disabled
	(1) "invisible": the control is not visible.		cleared
	(2)"cleared": the control is not visible but it still occupies space.		
styleclasses	CSS style classes separated by a blank.	Optional	panel-warning
			panel-success
			panel-danger
			panel-info
			ml-*
			mr-*

			mx-*
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
tabindex	(already explained above)		

BMOBILE:ROW

BMOBILE:ROW supports the responsive **grid system of Bootstrap**.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled cleared
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		cicarcu
	(3)"cleared": the control is not visible but it still occupies space.		
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	no-gutters
			row-cols-*
			row-cols-sm-*

			row-cols-md-*
			row-cols-lg-*
			row-cols-xl-*
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

BMOBILE:CONTAINER

A responsive container into which you add your controls, grids and other containers. You usually have exactly one BMOBILE:CONTAINER per page.

Basic			
takefullwidth	If set to "true" then the control takes all available horizontal	Optional	true
	width as its width. If set to "false" then the control does not have a predefined width but grows with its content.		false
takefullheight	Indicates if the content of the control's area gets the full	Optional	true
	available height.		false
	If you use percentage sizing inside the control's area then		
	this property must be switched to 'true'. If you use no		
	explicit vertical sizing at all - or you use vertical pixel sizing		
	for your controls - the property must be switched to 'false'.		
	Background information: container control's internally open		
	up a table in which you place rows (ITR/TR) which then		
	hold controls (e.g. LABEL/FIELD). The table that is opened up normally has no explicit height and grows with its		

	content as consequence. By specifying "takefullheight=true" the table itself is sized to fill the maximum height of the available area.		
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions		

	are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	
Accessibility		
role	If set a role attribute is added to the html for screen readers. Example values are: banner, main, navigation.	main banner contentinfo complementary navigation

BMOBILE:FORM, BMOBILE:FORMINLINE

These forms are more light-weight and flexible than BMOBILE: FORMAREA. Use the BMOBILE: FORMINLINE to add forms to bars like the BMOBILE: HORIZONTALBAR and the BMOBILE: SIDEBAR.

These forms are not supported for Bootstrap 3.

- Properties for BMOBILE:FORM
- Properties for BMOBILE:FORMINLINE

Properties for BMOBILE:FORM

Basic	Basic				
displayonly	If set to true, the FIELD will not be accessible for input. It is just used as an output field.	Optional	true false		
invisiblemode	If the visibility of the control is determined dynamically by an adapter property then there are two rendering modes if the visibility is "false": (1) "invisible": the control is not visible. (2)"cleared": the control is not visible but it still occupies space.	Optional	invisible disabled cleared		
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.				
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional			

styleclasses	CSS style classes separated by a blank.	Optional	d-none d-md-block d-none d-lg-block ml-*
			mr-*
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	Optional	
Miscellaneous testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

Properties for BMOBILE:FORMINLINE

Basic	Basic				
displayonly	If set to true, the FIELD will not be accessible for input. It is just used as an output field.	1	true false		
invisiblemode	If the visibility of the control is determined dynamically by an adapter property then there are two rendering modes if the visibility is "false":	Optional	invisible disabled cleared		
	(1) "invisible": the control is not visible.(2)"cleared": the control is not visible but it still occupies space.		Cleareu		

visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	d-none d-md-block d-none d-lg-block ml-* mr-*
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	Optional	
Miscellaneous	;		ı
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:FORMAREA

The surrounding container for forms. Within a BMOBILE:FORMAREA you can have several **BMOBILE:FORMGROUP** containers.

Basic			
legend	A caption shown for the formarea.	Optional	
legendprop	The name of the adapter parameter which dynamically defines the caption of the formarea at runtime.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
	Do not specify a "name" inside the control if specifying a "textid".		
invisiblemode	If the visibility of the control is determined dynamically by an adapter property then there are two rendering modes if the visibility is "false":	Optional	invisible disabled
	(1) "invisible": the control is not visible.		cleared
	(2)"cleared": the control is not visible but it still occupies space.		
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*

			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:FORMGROUP

Use this container to group several **BMOBILE:FLABEL** and input controls like **BMOBILE:FFIELD** within a form.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	d-none d-md-block d-none d-lg-block ml-* mr-*
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	Optional	
invisiblemode	If the visibility of the control is determined dynamically by an adapter property then there are two rendering modes if the visibility is "false": (1) "invisible": the control is not visible. (2)"cleared": the control is not visible but it still occupies space.	Optional	invisible disabled cleared
renderasrow	If set to TRUE FLABEL and corresponding FFIELD will be rendered horizontally in a row. If set to false they will be stacked vertically. Only supported for Bootstrap 4 and higher. Default is TRUE.	Optional	true false
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	

name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional		
Accessibility				
setinputlabel	If set to TRUE then the first label control in the form group is used as label for the following input controls. This association is understood by creenreaders. Default is FALSE.	Optional	true false	
namesronly	If set to TRUE then the name of the form group is only made accessible to screenreaders. It is not visually rendered. Default is FALSE.	Optional	true false	
Miscellaneous	Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional		

BMOBILE:LISTGROUP

A list group displays a number of items as a vertical list. Use LISTGROUP to selectively display a certain number of items.

No scrollbar or pagination is applied. For huge item numbers, consider using grid controls instead.

You can create listgroups with simple readonly items or listgroups with items that can be activated, and that can trigger events on the server and on the client.

Basic		
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional
changeindexprop	Name of the adapter parameter providing a value which indicates whether the control should be refreshed with new data on the client or not. A different value than the previous triggers the refresh. It does not need to be a higher value.	Optional
Binding		
disabledprop	Name of the adapter parameter that dynamically defines if the control is disabled or enabled at runtime. If the value at runtime is set to TRUE the control is visible but disabled. In	Optional

	COLTABAREA controls this property is only supported for IE.		
methodprop	Name of the adapter parameter that dynamically defines the name of the event that is sent to the adapter when the user selects the item.	Optional	
textprop	Name of the adapter parameter which dynamically provides the text for the marker at runtime.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
Appearance			
itemstyle	CSS style definition, which is applied to all items in the list	Optional	
	Examples:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine style settings by separating them with a semicolon.		
itemstyleclasses	CSS style classes separated by a blank. These classes are applied to all items in the list.	Optional	list-group-item-primary list-group-item-secondary list-group-item-success list-group-item-danger list-group-item-warning list-group-item-info list-group-item-light list-group-item-dark
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080	Optional	

	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
styleclasses	CSS style classes separated by a blank.	Optional	list-group-flush
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.		true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	_	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
badgeprop	Name of the adapter parameter which dynamically provides the text of the badge for an item at runtime.	Optional	
badgeposition	Position where a badge is rendered. Valid values are right and left. Default is right.	Optional	right left
iconurlprop	Name of the adapter parameter which dynamically provides the url of the icon for an item at runtime.	Optional	
iconposition	Position where an icon is rendered. Valid values are right and left. Default is left.	Optional	right left
Miscellaneous	•		1
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:SIDEBARCONTAINER, BMOBILE:SIDEBAR, BMOBILE:SIDE-BARGROUP, BMOBILE:HORIZONTALBAR, BMOBILE:CONTENT

These containers support frequently used patterns for modern responsive pages. Additional controls like BMOBILE: TOGGLER, BMOBILE: SIDEBARGROUP, BMOBILE: BARTEXT support corresponding functionality for flexible rendering of bars and arbitrary menus and controls inside the bars. You can put all kinds of containers like rows, panels or complete pages into the BMOBILE: CONTENT container.

When dragging the BMOBILE: SIDEBARCONTAINER control from the palette to your page layout, several controls are arranged as sub-controls under the BMOBILE: SIDEBARCONTAINER. You can arrange the controls differently, replace, add, remove containers and style them. You can add all kind of content as child nodes of the BMOBILE: CONTENT. You can also use the BMOBILE: HORIZONTALBAR without BMOBILE: SIDEBARCONTAINER.

The NaturalAjaxDemos contain a running example. These containers are not supported for Bootstrap 3.

The responsive view of the Natural Ajax Demos itself is an example for a usage of the side navigation controls.

- Properties for BMOBILE:SIDEBARCONTAINER
- Properties for BMOBILE:SIDEBAR
- Properties for BMOBILE:SIDEBARGROUP
- Properties for BMOBILE:HORIZONTALBAR
- Properties for BMOBILE:CONTENT

Properties for BMOBILE:SIDEBARCONTAINER

Basic			
	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*

			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

Properties for BMOBILE:SIDEBAR

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
toggleid	A string value which can be used in the BMOBILE:TOGGLER to toggle the visibility. The specified id must be unique within this layout.	-	
styleclasses	CSS style classes separated by a blank.	Optional	bg-dark bg-light bg-primary bg-secondary

			border border-primary border border-secondary border border-dark border border-light
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	Optional	
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
Miscellaneo	ous		
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

Properties for BMOBILE:SIDEBARGROUP

Basic			
	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	ml-*
			mr-*
			mx-*
			mx-sm-*

			mx-md-*
			mx-lg-*
			mx-xl-*
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

Properties for BMOBILE:HORIZONTALBAR

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	fixed-bottom bg-dark
			navmenu-dark
			bg-light
			navmenu-light
			navmenu-light
			navmenu-dark
			bg-primary
			bg-secondary
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		

	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	

Properties for BMOBILE:CONTENT

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	

1 7 7	u can individually influence the rendering	′ I I	
1	ou can specify any style sheet expressions		
Examples are:			
border: 1px soli	d #FF0000		
background-col	or: #808080		
You can combine	e expressions by appending and separating	5	
them with a sen	nicolon.		
Sometimes it is	useful to have a look into the generated		
HTML code in o	rder to know where direct style definition	5	
are applied. Pre	ss right mouse-button in your browser		
and select the "V	View source" or "View frame's source"		
function.			

BMOBILE: TABPANE, BMOBILE: VERTICAL TABPANE and BMOBILE: TAB

Use these controls to implement responsive tab controls. Inside a BMOBILE:TABPANE and a BMOBILE:VERTICALTABPANE you can define BMOBILE:TAB containers representing the individual tab pages between which you can navigate. All HTML code for all tabs will be generated into one HTML page.

- Properties for BMOBILE:TABPANE
- Properties for BMOBILE:VERTICALTABPANE
- Properties for BMOBILE:TAB

Properties for BMOBILE:TABPANE

Basic			
navmode	There are several rendering modes. For example set this property to nav-pills if you want the tabs to be rendered as pills.	1	nav-tabs nav-pills
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon.	Optional	

	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
styleclasses	CSS style classes separated by a blank.	Optional	col-*
			col-sm-*
			col-md-*
			col-lg-*
			col-xl-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
aspectratio	Defines the proportional relationship between width and height	Optional	1by1
	of the control. Example: 4by3		16by9
			21by9
			4by3
width	Width of the control.	Optional	100
	There are three possibilities to define the width:		120
	(A) You do not define a width at all. In this case the width of		140
	the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.		160
	(B) Pixel sizing: just input a number value (e.g. "100").		180
	(C) Percentage sizing: input a percantage value (e.g. "50%"). Pay		200
	attention: percentage sizing will only bring up correct results if the parent element of the control properly defines a width this		50%
	1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1	ĺ	İ

	a width then the rendering result may not represent what you expect.		
height	Height of the control.	Optional	100
	There are three possibilities to define the height:		150
	(A) You do not define a height at all. As consequence the control		200
	will be rendered with its default height. If the control is a container control (containing) other controls then the height of		250
	the control will follow the height of its content.		300
	(B) Pixel sizing: just input a number value (e.g. "20").		250
	(C) Percentage sizing: input a percentage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct results if		400
	the parent element of the control properly defines a height this control can reference. If you specify this control to have a height		50%
	of 50% then the parent element (e.g. an ITR-row) may itself define a height of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		100%
withcollapse	If set to true a small button is added to hide and show the navigation tabs.	Optional	true
	navigation tabs.		false

Properties for BMOBILE:VERTICALTABPANE

Basic			
navmode	There are several rendering modes. For example set this property to nav-pills if you want the tabs to be rendered as pills.	_	nav-tabs nav-pills
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your		

	browser and select the "View source" or "View frame's source" function.		
styleclasses	CSS style classes separated by a blank.	Optional	
panecolstyle	Inline CSS style settings applied to the pane.	Optional	
panecolstyleclasses	CSS style classes separated by a blank applied to the pane. For responsive pages it is recommended to apply	Optional	col-*
	one of the col-* classes to define the width.		col-md-*
			col-lg-*
			col-xl-*
			border border-primary
			border border-secondary
			border border-dark
			border border-ligh
navcolstyle	Inline CSS style settings applied to the navigation tabs.	Optional	
navcolstyleclasses	CSS style classes separated by a blank applied to the navigation tabs. For responsive pages it is recommended	Optional	col-auto
	to apply one of the col-* classes to define the width.		col
			col-*
			col-sm-*
			col-md-*
			col-lg-*
			col-xl-*
			offset-*
			offset-sm-*
			offset-md-*
			offset-lg-*
			offset-xl-*
			mx-auto
			btn-group

			btn-group-vertica
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
aspectratio	Defines the proportional relationship between width and height of the control. Example: 4by3	Optional	
			16by9
			21by9
			4by3
width	Width of the control.	Optional	100
	There are three possibilities to define the width:		120
	(A) You do not define a width at all. In this case the width of the control will either be a default width or - in		140
	case of container controls - it will follow the width that		160
	is occupied by its content.		180
	(B) Pixel sizing: just input a number value (e.g. "100").		200
	(C) Percentage sizing: input a percantage value (e.g. "50%"). Pay attention: percentage sizing will only bring		50%
	up correct results if the parent element of the control properly defines a width this control can reference. If		100%
	you specify this control to have a width of 50% then the parent element (e.g. an ITR-row) may itself define a		
	width of "100%". If the parent element does not specify		
	a width then the rendering result may not represent what you expect.		
height	Height of the control.	Optional	100
	There are three possibilities to define the height:		150
	(A) You do not define a height at all. As consequence		200
	the control will be rendered with its default height. If the control is a container control (containing) other		250
	controls then the height of the control will follow the height of its content.		300
	(B) Pixel sizing: just input a number value (e.g. "20").		250
	(C) Percentage sizing: input a percentage value (e.g.		400
	"50%"). Pay attention: percentage sizing will only bring up correct results if the parent element of the control		50%
	properly defines a height this control can reference. If you specify this control to have a height of 50% then the		100%
	parent element (e.g. an ITR-row) may itself define a		

height of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		
If set to true a small button is added to hide and show the navigation tabs.	Optional	true false

Properties for BMOBILE:TAB

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
	Do not specify a "name" inside the control if specifying a "textid".		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
invisiblemode	This property has three possible values:	Optional	invisible
nvisionemode	(1) "invisible": the control is not visible without occupying any space.	- F	disabled
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		
	(3)"cleared": the control is not visible but it still occupies space.		
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
openmethod	Name of the event that is sent to the adapter when the user does a "tab" selection. The index of the "tab" that is opened can be transferred to the adapter by using the property OPENEDINDEXPROP.	Optional	
style	CSS style definition that is directly passed into this control.	Optional	

	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border
			border-secondary
			border
			border-dark
			border border-light
comment	Comment without any effect on rendering and behaviour. The	Optional	
	comment is shown in the layout editor's tree view.		

BMOBILE:TABSUBPAGES, BMOBILE:VERTICALTABSUBPAGES, BMOBILE:STRAIGHTTAB and BMOBILE:PAGER

The controls implement responsive tab controls. A BMOBILE:TABSUBPAGES control and a BMOBILE:VERTICALTABSUBPAGES control can have static tabs and dynamically defined tabs. The static tabs are added via BMOBILE:STRAIGHTTAB controls at design time. The HTML code is generated into the page holding the BMOBILE:TABSUBPAGES/BMOBILE:VERTICALSUBPAGES control.

- Properties for BMOBILE:TABSUBPAGES
- Properties for BMOBILE:VERTICALTABSUBPAGES
- Properties for BMOBILE:STRAIGHTTAB
- Properties for BMOBILE:PAGER

For the Adapter Interface and Built-In Events see the corresponding sections in *ROWTABSUBPAGES* and *STRAIGHTTABPAGE*.

In addition, the adapter interface may optionally contain a STRAIGHTTABCOUNT and/or a level field:

```
2 STRAIGHTTABCOUNT (I4)
2 TABITEMS (1:*)
3 LEVEL (I4)
```

STRAIGHTTABCOUNT

The count of static tabs. This is useful to conveniently calculate the index in the array of the dynamically defined tabs.

LEVEL

Drop down menus are supported. The level defines whether it is a sub item in a dropdown menu or a root item. By adding an optional BMOBILE:PAGER, short cut links for the previous clicked tabs will be added.

For more information see the corresponding samples in the NaturalAjaxDemos.

Properties for BMOBILE:TABSUBPAGES

Basic			
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
navmode	There are several rendering modes. For example set this property to nav-pills if you want the tabs to be rendered as pills.	Optional	nav-tabs nav-pills
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	bg-light ml-* mr-* mx-* mx-sm-* mx-md-* mx-lg-* mt-* mb-* mb-* border border-primary

comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	border border-secondary border border-dark border border
aspectratio	Defines the proportional relationship between width and height of the control. Example: 4by3	Optional	1by1 16by9 21by9 4by3
width	Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content. (B) Pixel sizing: just input a number value (e.g. "100"). (C) Percentage sizing: input a percantage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct results if the parent element of the control properly defines a width this control can reference. If you specify this control to have a width of 50% then the parent element (e.g. an ITR-row) may itself define a width of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		100 120 140 160 180 200 50% 100%
height	Height of the control. There are three possibilities to define the height: (A) You do not define a height at all. As consequence the control will be rendered with its default height. If the control is a container control (containing) other controls then the height of the control will follow the height of its content. (B) Pixel sizing: just input a number value (e.g. "20"). (C) Percentage sizing: input a percentage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct		100 150 200 250 300 250 400

	results if the parent element of the control properly defines a height this control can reference. If you specify this control to have a height of 50% then the parent element (e.g. an ITR-row) may itself define a height of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		100%
triggerserver	Flag indicating whether the adapter should be triggered if the user switches between pages. If set to true, method trigger() inside the TABSUBPAGESInfo object is called - before switching the page. Therefore the adapter can abort a page switch - maybe a user has to enter some data first on the current page before switching to another one.	•	true false
withcollapse	If set to true a small button is added to hide and show the navigation tabs.	Optional	true false
withdropdown	If set to true tabs can have drop-down menus. An additional Natural field level is generated.	Optional	true false

Properties for BMOBILE:VERTICALTABSUBPAGES

Basic			
navmode	There are several rendering modes. For example set this property to nav-pills if you want the tabs to be rendered as pills.	•	nav-tabs nav-pills
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	

panecolstyle	Inline CSS style settings applied to the pane.	Optional	
panecolstyleclasses	CSS style classes separated by a blank applied to the pane. For responsive pages it is recommended to apply	Optional	col-*
	one of the col-* classes to define the width.		col-md-*
			col-lg-*
			col-xl-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
navcolstyle	Inline CSS style settings applied to the navigation tabs.	Optional	
navcolstyleclasses	CSS style classes separated by a blank applied to the	Optional	col-auto
	navigation tabs. For responsive pages it is recommended to apply one of the col-* classes to define the width.		col
			col-*
			col-sm-*
			col-md-*
			col-lg-*
			col-xl-*
			offset-*
			offset-sm-*
			offset-md-*
			offset-lg-*
			offset-xl-*
			mx-auto
			btn-group
			btn-group-vertical

comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
aspectratio	Defines the proportional relationship between width and height of the control. Example: 4by3	Optional	1by1 16by9 21by9 4by3
width	Width of the control.	Optional	100
	There are three possibilities to define the width:		120
	(A) You do not define a width at all. In this case the width of the control will either be a default width or - in case		140
	of container controls - it will follow the width that is		160
	occupied by its content.		180
	(B) Pixel sizing: just input a number value (e.g. "100").		200
	(C) Percentage sizing: input a percantage value (e.g. "50%"). Pay attention: percentage sizing will only bring		50%
	up correct results if the parent element of the control properly defines a width this control can reference. If you specify this control to have a width of 50% then the parent element (e.g. an ITR-row) may itself define a width of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		100%
height	Height of the control.	Optional	100
	There are three possibilities to define the height:		150
	(A) You do not define a height at all. As consequence the control will be rendered with its default height. If the		200
	control is a container control (containing) other controls		250
	then the height of the control will follow the height of its content.		300
	(B) Pixel sizing: just input a number value (e.g. "20").		250
	(C) Percentage sizing: input a percentage value (e.g.		400
	"50%"). Pay attention: percentage sizing will only bring up correct results if the parent element of the control		50%
	properly defines a height this control can reference. If you specify this control to have a height of 50% then the parent element (e.g. an ITR-row) may itself define a height of "100%". If the parent element does not specify		100%

	a width then the rendering result may not represent what you expect.		
1	If set to true a small button is added to hide and show the navigation tabs.	Optional	true false
1 *	If set to true tabs can have drop-down menus. An additional Natural field level is generated.	Optional	true false

Properties for BMOBILE:STRAIGHTTAB

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	Optional	
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	-	true false
invisiblemode	This property has three possible values: (1) "invisible": the control is not visible without occupying any space. (2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more. (3) "cleared": the control is not visible but it still occupies space.	Optional	invisible disabled
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
style	CSS style definition that is directly passed into this control.	Optional	

	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	

Properties for BMOBILE:PAGER

Basic		
styleclasses	CSS style classes separated by a blank.	Optional
style	CSS style definition that is directly passed into this control.	Optional
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:	
	border: 1px solid #FF0000	
	background-color: #808080	
	You can combine expressions by appending and separating them with a semicolon.	
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional
maxcount	Maximum number of pager buttons. Each pager button holds a link for the last clicked tab.	Optional

7 Responsive Grids

	BMOBILE:ICONCOL	148
	BMOBILE:SIMPLECOL	150
	BMOBILE:SIMPLEGRID	
	BMOBILE:SIMPLEHEADERCOL	
	BMOBILE:SIMPLEHEADERROW	
	BMOBILE:SIMPLEROW	
_	DIVIODICE.ONI ELICOV	100

BMOBILE:ICONCOL

An icon column in a responsive grid.

Basic			
iconurl	URL of image that is displayed inside the control. Any image type (.gif, .jpg,) that your browser does understand is valid.	Optional	
	Use the following options to specify the URL:		
	(A) Define the URL relative to your page. Your page is generated directly into your project's folder. Specifiying "images/xyz.gif" will point into a directory parallel to your page. Specifying "/HTMLBasedGUI/images/new.gif" will point to an image of a neighbour project.		
	(B) Define a complete URL, like "http://www.softwareag.com/images/logo.gif".		
iconurlprop	Name of adapter parameter that provides as value the URL of the image that is shown inside the control.	Optional	
method	Name of the event that is sent to the adapter when clicking on the control.	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		
	(3)"cleared": the control is not visible but it still occupies space.		
title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		

Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
CSS style classes separated by a blank.	Optional	icon-svg-primary
		ml-*
		mr-*
CSS style definition that is directly passed into this control.	Optional	
With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
border: 1px solid #FF0000		
background-color: #808080		
You can combine expressions by appending and separating them with a semicolon.		
Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2		
	the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control. If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true". CSS style classes separated by a blank. CSS style classes separated by a blank. CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function. If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be	the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control. If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true". CSS style classes separated by a blank. Optional With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function. If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be

, ,	If the control shall be bound to a Natural system variable of	_	
I .	string format with the attribute njx:natsysvar, this attribute		
	indicates the format of the string, A (code page) or U		
	(Unicode). The default is A.		
njx:natcomment	The value of this attribute is generated as comment line into	Optional	
	the parameter data area of the Natural adapter, before the		
	field name. The Map Converter, for instance, uses this		
	attributes to indicate for a generated statusprop variable to		
	which field the statusprop belongs.		

BMOBILE:SIMPLECOL

A column in a responsive grid.

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
visible	If set to FALSE the column is not visible in the browser but the corresponding data is still accessable from within the Natural application. Example usage is an "id column".	Optional	true
displayonly	If set to true, the FIELD will not be accessible for input. It is just used as an output field.	Optional	true false
colprop	Name of the adapter parameter that dynamically defines the grid column value.	Obligatory	
flush	Flushing behaviour of the input control. By default an input into the control is registered within the browser client - and communicated to the server adapter object when a user e.g. presses a button. By using the FLUSH property you can change this behaviour. Setting FLUSH to "server" means that directly after changing the input a synchronization with the server adapter is triggered. As consequence you directly can react inside your adapter logic onto the change of the corresponding value Please be aware of that during the synchronization always all changed properties - also the		screen

	ones that were changed before - are transferred to the adapter object, not only the one that triggered the synchonization. Setting FLUSH to "screen" means that the changed value is populated inside the page. You use this option if you have redundant usage of the same property inside one page and if you want to pass one changed value to all its representation directly after changing the value.		
flushmethod	When the data synchronization of the control is set to FLUSH="server" then you can specify an explicit event to be sent when the user updates the content of the control. By doing so you can distinguish on the server side from which control the flush of data was triggered.	Optional	
datatype	By default, the control is managing its content as string. By explicitly setting a datatype you can define that the control will format the data coming from the server: if the field has datatype "date" and the user inputs "010304" then the input will be translated into "01.03.2004" (or other representation, dependent on date format settings). Please note: the datatype "float" is named a bit misleading -it represents any decimal format number. The server side representation may be a float value, but also can be a double or a BigDecimal property.	Optional	date float int long time timestamp color xs:decimal xs:double xs:date xs:dateTime xs:time N n.n P n.n string n L xs:boolean xs:byte xs:short

Natural			
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	•	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.		

BMOBILE:SIMPLEGRID

A responsive grid.

If the grid has been configured for server-side scrolling and sorting, a data structure is generated that contains fields controlling server-side scrolling and sorting. In addition, specific server-side scrolling events are triggered. The data structure is identical to the corresponding data structure in non-responsive grids.

For more information see section on controls that support Server-Side Scrolling and Sorting.

For details see the corresponding samples in the NaturalAjaxDemos.

Adapter Interface (Server-Side Scrolling and Sorting)

For a grid

```
<bmobile:simplegrid gridprop="lines" serverside="true" ...>
```

the following data structure is generated.

```
1 LINESINFO
2 ROWCOUNT (I4)
2 SIZE (I4)
2 SORTPROPS (1:*)
3 ASCENDING (L)
3 PROPNAME (U) DYNAMIC
2 TOPINDEX (I4)
```

Built-in Events (Server-Side Scrolling and Sorting)

Scrolling Events (Natural Server-Side Scrolling and Sorting only)

value-of-gridprop.onTopindexChanged

Basic			
gridprop	Name of the adapter parameter that represents the control in the adapter.	Optional	
width	Width of the control.	Optional	100
	There are three possibilities to define the width:		120
	(A) You do not define a width at all. In this case the		140
	width of the control will either be a default width or - in case of container controls - it will follow the width		160
	that is occupied by its content.		180
	(B) Pixel sizing: just input a number value (e.g. "100").		200
	(C) Percentage sizing: input a percantage value (e.g. "50%"). Pay attention: percentage sizing will only bring		50%
	up correct results if the parent element of the control properly defines a width this control can reference. If		100%
	you specify this control to have a width of 50% then the		
	parent element (e.g. an ITR-row) may itself define a width of "100%". If the parent element does not specify		
	a width then the rendering result may not represent what you expect.		
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
source	The kind of data source like string, file, url.	Optional	prop
			file
			url

sourcelocation	The source location. Depends on the kind of source. Examples: ./autocomplete/myfile, http://myremotedatasource	Optional	
sourcelocationprop	Name of the adapter parameter that specifies the sourcelocation dynamically at runtime.	Optional	
changeindexprop	Name of the adapter parameter providing a value which indicates whether the control should be refreshed with new data on the client or not. A different value than the previous triggers the refresh. It does not need to be a higher value.	Optional	
selectprop	Name of the adapter parameter representing the selected item	Optional	
selectonclick	When clicking an item in a row, the row is marked as selected and rendered in a different color. If the property selectprop has been set, the corresponding Natural data fields are filled with the values of the selected row. If you don't want this, set this property to FALSE.	Optional	true false
features	Customize the rendering of the grid. Example: "autoWidth:false	Optional	lengthChange:false ordering:false paging:false searching:false info:false
triggersearchprop	The name of the adapter parameter which dynamically defines the search value at runtime. Set this property if you want to set the search value and trigger the search automatically from your Natural program.	Optional	
Appearance		·	
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style	Optional	

	your browser and select the "View source" or "View frame's source" function.		
styleclasses	CSS style classes separated by a blank.	Optional	table-striped table-bordered
			table-borderless
			table-dark
			table-sm
			w-100
			vw-100
withkeyboardfocus	Set this property to TRUE to enable keyboard navigation	Optional	true
	for columns, rows and pages.		false
frozencolumnsleft	Number of columns, which should be horizontally	Optional	1
	frozen to the left.		2
			3
			int-value
frozencolumnsright	Number of columns, which should be horizontally frozen to the right.	Optional	1
			2
			3
			int-value
Scrolling and Sorting	g	l .	l
serverside	When set to true Server-Side Scrolling and Sorting is done. Per default Web Server-Side Scrolling is used. To switch on Natural Server-Side Scrolling: Apply a size value at runtime in the corresponding generated grid info data structure.	Optional	true false
sortcol	Index of the initial sorted column. Index starts with 0.	Optional	
sortorder	Sort order (asc or desc) of the initial sorted column.	Optional	
scroller	When set to TRUE a scrollbar is used instead of a pager. This requires to also set the scrollheight property.	Optional	true false
scrollheight	If scroller is not set to TRUE, this property is ignored. Use this property to set the scrolling height of the grid.	Optional	100

			150
			200
			250
			300
			250
			400
			50%
			100%
rowcount	If scroller is set to TRUE this property is ignored. Use this property to set the inital count of rows per page for	Optional	1
	the pager.		2
			3
			int-value
rowcountmenu	Use this property to customize the drop-down menu for the row count values per page. Example: 10	Optional	
serverwait	Time in milliseconds the browser client will wait for	Optional	200
	the requested server items. Allowed values are 200 - 1000. Default is 200. Only used for server-side scrolling		300
	and sorting.		400
			500
			600
			700
Natural			
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may	Optional	

	be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	_	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification		

BMOBILE:SIMPLEHEADERCOL

A header column in a responsive grid.

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		true false
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	Optional	
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	

titletextid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
	Do not specify a "name" inside the control if specifying a "textid".		
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and	Optional	
styleclasses	celect the "View source" or "View frame's source" function. CSS style classes separated by a blank.	Optional	d-none d-md-block d-none d-lg-block text-uppercase font-italic font-weight-bold font-weight-bolder font-weight-light font-weight-lighter
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	

BMOBILE:SIMPLEHEADERROW

A row container which contains the header columns in a responsive grid.

Properties

Basic			
styleclasses	CSS style classes separated by a blank.	Optional	
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	

BMOBILE:SIMPLEROW

A row container which contains the columns in a responsive grid.

Basic		
onclickmethod	Name of the event that is sent to the adapter when the user clicks.	Optional
ondblclickmethod	Name of the event that is sent to the adapter when the user double clicks.	Optional
	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional

8 Responsive Trees

RMORII E:DATATREE	16	30
	 	JZ

BMOBILE:DATATREE

A responsive data tree control. Use this control to show tree data structures with a depth > 2 and/or many items. For navigation purposes use the BMOBILE:NAVMENU control instead.

When a node is opened, the control also supports dynamically loading subtrees: Set property dynamicloading="true".

In case the subnodes of the opened node have not yet been loaded, the built-in event value-of-valueprop.reactOnToggle will be triggered.

To switch on multiselection, set property singleselect="false".

As default, the event value-of-valueprop.reactOnSelect is sent to Natural when an item is selected or unselected. When the escape key is pressed, all items will be deselected. In this case the event value-of-valueprop.reactOnClearSelection is sent to Natural.

To prevent neither events from being sent to Natural on each selection change, set the property triggerserver="false".

- Adapter Interface
- Built-in Events
- Properties

Adapter Interface

For a BMOBILE:DATATREE control with valueprop="mytree" the following adapter interface is generated:

```
1 MYTREE (1:*)
2 LEVEL (I4) /* level starts with 1
2 OPENED (I4) /* 0: closed, 1: opened, 2: end node
2 SELECTED (L) /* TRUE or FALSE whether the item is selected
2 TEXT (A) DYNAMIC /* text of the node
```

You can dynamically set tooltip texts on nodes from within your Natural program. For a BMOBILE:DATATREE with the following property settings ...

```
<bmobile:datatree valueprop="mytree" titleprop="mytooltip" ...</pre>
```

the following adapter interface is generated:

```
1 MYTREE (1:*)
2 LEVEL (I4) /* level starts with 1
2 MYTOOLTIP (A) DYNAMIC
2 OPENED (I4) /* 0: closed, 1: opened, 2: end node
2 SELECTED (L) /* TRUE or FALSE whether the item is selected
2 TEXT (A) DYNAMIC /* text of the node
```

Built-in Events

value-of-valueprop.reactOnSelect	triggered when the selection on nodes changes in the user interface
value-of-valueprop.reactOnToggle	triggered when the dynamicloading is switched on and the subnodes of the opened node have not yet been loaded
value-of-valueprop.reactOnClearSelection	triggered when the escape key is pressed and all items are deselected

Optionally, reacting to double click events is possible:

Set property ondblclickmethod="myondblclick". This will trigger value-of-valueprop.myondblclick when a node is double clicked.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
triggerserver	Per default the event reactOnSelect is sent to Natural when the selection of an item is changed. Set this property to "false" if you don't want this event to be sent.	Optional	true false
openonselect	If set to TRUE not only a click on the corresponding icons but also the selection of the text will automatically open the tree node. Default is TRUE.		true false
Binding			
valueprop	(already explained above)		
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
ondblclickmethod	Name of the event that is sent to the adapter when the user double clicks.	Optional	
Appearance		ı	1

styleclasses	CSS style classes separated by a blank.	Optional	bg-light
			ml-*
			mr-*
			mx-*
			mx-sm-*
			mx-md-*
			mx-lg-*
			mx-xl-*
			mt-*
			mb-*
			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		
dynamicloading	If set to "true" then you indicate to the tree control that not all tree information may be loaded when initializing the tree (i.e. the tree collection on server side). As consequence the tree control will pass the "toggle-event" to the server - in case the subnodes of a certain nodes are not yet loaded. In the case the toggle event is passed to the server, the method onToggle() is called inside the tree item.	Optional	true false
hscroll	Set this property if you did define a limitted width for the surrounding container. Default is that contents is cut ("hidden"). You can define that scrollbars are shown if the content is exceeding the control's container ("auto"). Or scrollbars can be shown always ("scroll").	Optional	auto scroll hidden
size	Set this property to render the tree smaller or larger. Valid values are "sm" and "lg".	Optional	sm lg
singleselect	If set to "true" then only one item can be selected. If set to "false" then multiple icons can be selected.	Optional	true false
iconclassopened	Icon of a tree node that has subnodes and that is currently showing its nodes. The icon is defined as css class. You can use the Bootstrap Icons library. Example: bi-folder2-open.	Optional	
iconclassclosed	Icon of a tree node that has subnodes and that is currently not showing its nodes. The icon is defined as css class. You can use the Bootstrap Icons library. Example: bi-folder2.	Optional	
iconclassendnode	Icon of a tree node that is an end node (leaf node). The icon is defined as css class. You can use the Bootstrap Icons library. Example: bi-file-richtext.	Optional	
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		

Miscellaneous		
	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	

9 Responsive Menus

BMOBILE:NAVBAR	1	6	8
BMOBILE:NAVMENU	1	7	(

BMOBILE:NAVBAR

A responsive navigation bar.

Basic			
menuprop	Name of the adapter parameter that represents the control in the adapter.	Obligatory	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
styleclasses	CSS style classes separated by a blank.	Optional	fixed-bottom bg-dark navmenu-dark bg-light navmenu-light navmenu-light navmenu-dark bg-primary bg-secondary
style	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
brandprop	Name of the adapter parameter that dynamically defines a brand image.	Optional	

brandstraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".	Optional	true false
title	Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
Natural			
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	Optional	
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	

BMOBILE:NAVMENU

A menu container you can add to the BMOBILE: SIDEBAR or BMOBILE: HORIZONTALBAR container. The generated Natural Adapter Interface is identical to the Adapter Interface of the BMOBILE: NAVTREE:

Adapter Interface

For a BMOBILE: NAVMENU control with valueprop="mymenu" the following adapter interface is generated:

```
1 NAVMENU (1:*)
2 LEVEL (I4) /* level starts with 1
2 OPENED (I4) /* 0:normal node; 2: end node
2 SELECTED (L) /* TRUE or FALSE whether the item is selected
2 TEXT (A) DYNAMIC /* text of the node
```

Built-in Events

For a BMOBILE: NAVMENU control with valueprop="mymenu" the event mymenu.onSelectMenuItem is triggered when selecting an end node.

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
styleclasses	CSS style classes separated by a blank.	Optional	bg-light ml-* mr-* mx-* mx-sm-* mx-md-* mx-lg-*
			mt-*

			my-*
			border border-primary
			border border-secondary
			border border-dark
			border border-light
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
Natural			J.
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	Optional	
njx:natstringtype	If the control shall be bound to a Natural system variable	Optional	
	of string format with the attribute njx:natsysvar, this		

	attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.		
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.		
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

10 Responsive Chart Controls

RCHART and RCHARTDATA	17	74
RPIECHART	18	8.7

The controls can be integrated into mobile pages and into other pages. The charts are built using the tool chart.js, see http://www.chartjs.org/

RCHART and RCHARTDATA

The RCHART control supports rendering the following charts:

- line charts
- bar charts
- horizontal bar charts

An RCHART control can have several RCHARTDATA controls as sub controls. Each RCHARTDATA control describes rendering and data for the datasets shown in the chart.

Example

Several examples and corresponding description are provided in the Natural for Ajax demos.

Properties for RCHART

Basic			
rcharttype	Type of the chart. Examples: bar,horizontalBar,line.	Optional	bar horizontalBar line
rcharttypeprop	Name of the adapter parameter that provides as value the type of the chart. Valid values are line, bar, horizontalBar	_	
labels	Semicolon separated list. Example: 2015;2016;2017. In a bar chart these are the labels shown for the x-axis. In a horizontal bar chart these are the labels shown for the y-axis.	Optional	
labelstextid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	-	
labelsprop	Name of the adapter parameter, which contains the label values. The field is generated as child of the valueprop field.	Optional	label1;label2;label3

valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
styleclasses	CSS style classes separated by a blank.	Optional	
stackedxaxis	If set to true the bars or lines of the chart are	Optional	true
	stacked on the x-axis.		false
stackedyaxis	If set to true the bars or lines of the chart are stacked on the y-axis.	Optional	true
			false
selectedlabelprop	Name of the adapter parameter to which the value of the selected label is set on click.	Optional	
changeindexprop	Name of the adapter parameter providing a value which indicates whether the control should be refreshed with new data on the client or not. A different value than the previous triggers the refresh. It does not need to be a higher value.	Optional	
showvalueinchart	Show the values in the chart. Per default the	Optional	true
	values are shown as tooltip.		false
showvaluepos	If set to inside the values are shown inside the	Optional	inside
	chart. If set to outside the values are set outside the chart. Default is inside.		outside
showtooltip	If set to false tooltips are disabled. Default is true.	Optional	true
			false

showvaluefontfamily	The font family which is used to show the value.	Optional	
showvaluefontstyle	The font style which is used to show the value.	Optional	
showvaluefontsize	The font size which is used to show the value.	Optional	1
			2
			3
			int-value
showvaluefontcolor	Color of the control. Value must follow format "#rrggbb", e.g. #000000 for black.	Optional	#FF0000
			#00FF00
			#0000FF
			#FFFFFF
			#808080
			#000000
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
BarOptions			
xaxisscalelabel	The text for the label of the scale for this axis.	Optional	
xaxisscaletextid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
	Do not specify a "name" inside the control if specifying a "textid".		
yaxisscalelabel	The text for the label of the scale for this axis.	Optional	
yaxisscaletextid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
	Do not specify a "name" inside the control if specifying a "textid".		
xaxisbarthickness	Width of the bars in pixels. If not set, the bars are	Optional	20
	sized automatically.		30
			40
			50
			60

xaxisbarpercentage Percent (0-1) of the available width each bar should be within the category percentage. 1.0 will take the whole category width and put the bars right next to each other. Axaiscategorypercentage Percent (0-1) of the available width (the space between the gridlines for small datasets) for each data-point to use for the bars. Optional 0.5 0.6 0.7 0.8 0.9 1.0 yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. Optional 10 LineOptions Showlines If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.				
will take the whole category width and put the bars right next to each other. 0.5 0.7 0.8 0.9 1.0 xaxiscategorypercentage Percent (0-1) of the available width (the space between the gridlines for small datasets) for each data-point to use for the bars. Optional 0.5 0.6 0.7 0.8 0.9 1.0 yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. Optional 10 LineOptions Showlines If set to false the line is not drawn for this dataset. Optional false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content	xaxisbarpercentage		Optional	0.4
xaxiscategorypercentage Percent (0-1) of the available width (the space between the gridlines for small datasets) for each data-point to use for the bars. Percent (0-1) of the available width (the space between the gridlines for small datasets) for each data-point to use for the bars. Optional 0.5 0.6 0.7 0.8 0.9 1.0 0.9 1.0 0.5 0.9 0.9 1.0 0.5 0.9 0.9 0.9 0.9 0.9 0.9 0.9 0.9 0.9 0.9		will take the whole category width and put the		0.5
xaxiscategorypercentage Percent (0-1) of the available width (the space between the gridlines for small datasets) for each data-point to use for the bars. Qptional 0.5 0.6 0.6 0.7 0.8 0.9 0.9 1.0 0.8 0.9 1.0 0.9 1.0 0.5 0.6 0.9 0.9 1.0 0.5 0.6 0.9 0.9 1.0 0.5 0.6 0.0 0.9 0.9 0.0 0.0 0.0 0.0 0.0 0.0 0.0		bars right next to each other.		0.7
xaxiscategorypercentage Percent (0-1) of the available width (the space between the gridlines for small datasets) for each data-point to use for the bars. Description Description				0.8
xaxiscategorypercentage Percent (0-1) of the available width (the space between the gridlines for small datasets) for each data-point to use for the bars. Optional 0.5 0.6 0.7 0.8 0.9 1.0 yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. Optional 20 30 40 50 60 LineOptions If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occuried by its content.				0.9
between the gridlines for small datasets) for each data-point to use for the bars. 0.6 0.7 0.8 0.9 1.0 yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. Optional sized automatically. Showlines If set to false the line is not drawn for this dataset. Showlines If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occurried by its content follows the width that is occurried by its content.				1.0
data-point to use for the bars. 0.6 0.7 0.8 0.9 1.0 1.0 yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. 30 40 50 60 LineOptions showlines If set to false the line is not drawn for this dataset. Miscellaneous true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occurred by its content.	xaxiscategorypercentage	_	_	0.5
yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. Height of the bar in pixels. If not set, the bars are sized automatically. Optional 20 30 40 50 60 LineOptions showlines If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width or - in case of container controls - it will follow the width that is occupied by its content				0.6
yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. Height of the bar in pixels. If not set, the bars are sized automatically. Optional 40 50 60 LineOptions showlines If set to false the line is not drawn for this dataset. Optional false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. Optional 100 There are three possibilities to define the width: (A) You do not define a width at all. In this case the width or in case of container controls - it will follow the width that is occupied by its content.				0.7
yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. Optional 20 30 40 50 60 LineOptions showlines If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.				0.8
yaxisbarthickness Height of the bar in pixels. If not set, the bars are sized automatically. Description 20				0.9
sized automatically. 30 40 50 60 LineOptions showlines If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. (A) You do not define a width at all. In this case the width or - in case of container controls - it will follow the width that is occupied by its content.				1.0
LineOptions Showlines If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. Optional Optional 100 There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.	yaxisbarthickness		Optional	20
LineOptions showlines If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.		sized automatically.		30
LineOptions showlines If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.				40
LineOptions showlines				50
showlines If set to false the line is not drawn for this dataset. Optional true false Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.				60
Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.	LineOptions			1
Miscellaneous testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification width Width of the control. Optional 100 There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.	showlines	If set to false the line is not drawn for this dataset.	Optional	true
testtoolid Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification Width of the control. Optional Optional 100 There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.				false
identifier that can be later on used within your test tool in order to do the object identification Width of the control. Optional 100 There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.	Miscellaneous			1
There are three possibilities to define the width: (A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.	testtoolid	identifier that can be later on used within your	Optional	
(A) You do not define a width at all. In this case the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.	width	Width of the control.	Optional	100
the width of the control will either be a default width or - in case of container controls - it will follow the width that is occupied by its content.		There are three possibilities to define the width:		120
width or - in case of container controls - it will follow the width that is occupied by its content.				140
follow the width that is occupied by its content.		width or - in case of container controls - it will		160
		follow the width that is occupied by its content.		180

	(B) Pixel sizing: just input a number value (e.g. "100"). (C) Percentage sizing: input a percantage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct results if the parent element of the control properly defines a width this control can reference. If you specify this control to have a width of 50% then the parent element (e.g. an ITR-row) may itself define a width of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.		200 50% 100%
height	Height of the control. There are three possibilities to define the height: (A) You do not define a height at all. As consequence the control will be rendered with its default height. If the control is a container control (containing) other controls then the height of the control will follow the height of its content. (B) Pixel sizing: just input a number value (e.g. "20"). (C) Percentage sizing: input a percentage value (e.g. "50%"). Pay attention: percentage sizing will only bring up correct results if the parent element of the control properly defines a height this control can reference. If you specify this control to have a height of 50% then the parent element (e.g. an ITR-row) may itself define a height of "100%". If the parent element does not specify a width then the rendering result may not represent what you expect.	Optional	100 150 200 250 300 250 400 50% 100%

Properties for RCHARTDATA

Basic		
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	
label	The text for the label of this dataset.	Optional
labeltextid	Multi language dependent text that is displayed inside the control. The "textid"	Optional

	is translated into a corresponding string at runtime.		
	Do not specify a "name" inside the control if specifying a "textid".		
datatype	By default, the control is managing its	Optional	date
	content as string. By explicitly setting a datatype you can define that the control		float
	will format the data coming from the server: if the field has datatype "date" and		int
	the user inputs "010304" then the input will be translated into "01.03.2004" (or		long
	other representation, dependent on date		time
	format settings).		timestamp
	Please note: the datatype "float" is named a bit misleading - it represents any		color
	decimal format number. The server side representation may be a float value, but		xs:decimal
	also can be a double or a BigDecimal property.		xs:double
	F		xs:date
			xs:dateTime
			xs:time
			N n.n
			P n.n
			string n
			L
			xs:boolean
			xs:byte
			xs:short
backgroundcolor	The fill color of the bars or the fill color	Optional	#ffff00
	under the lines or the fill color of the arcs depending on the chart type.		rgb(255, 255, 0)
			hsl(60, 100%, 50%)
borderwidth	Border width in pixels.	Optional	2
			4

			6
bordercolor	Border color.	Optional	#ffff00 rgb(255, 255, 0) hsl(60, 100%, 50%)
onclickmethod	The event which is triggered in the Natural program when for instance a bar of a bar chart is clicked.	Optional	
legendclickmethod	Name of the event which is triggered when clicking on a legend.	Optional	
Bar			•
hoverbackgroundcolor	Background color when hovered.	Optional	#ffff00 rgb(255, 255, 0) hsl(60, 100%, 50%)
hoverborderwidth	Border width in pixel when hovered.	Optional	2 4 6
hoverbordercolor	Border color when hovered.	Optional	#ffff00 rgb(255, 255, 0) hsl(60, 100%, 50%)
Line	I		
borderdash	Length and spacing of dashes separated by semicolon. Example: 10	Optional	10;2
pointbordercolor	The border color for points.	Optional	#ffff00 rgb(255, 255, 0) hsl(60, 100%, 50%)
pointbackgroundcolor	The fill color for points	Optional	#ffff00 rgb(255, 255, 0) hsl(60, 100%, 50%)
pointborderwidth	The width of the point border in pixels	Optional	2

			6
pointradius	The radius of the point shape. If set to 0, nothing is rendered.	Optional	7 15
pointhoverradius	The radius of the point when hovered.	Optional	7
pointhitradius	The pixel size of the non-displayed point that reacts to mouse events.	Optional	7 15
pointhoverbackgroundcolor	Point background color when hovered.	Optional	#ffff00 rgb(255, 255, 0) hsl(60, 100%, 50%)
pointhoverbordercolor	Point border color when hovered.	Optional	#ffff00 rgb(255, 255, 0) hsl(60, 100%, 50%)
pointhoverborderwidth	Border width of point when hovered	Optional	2 4 6
pointstyle	The style of point. Options are : circle, triangle, rect, rectRounded, rectRot, cross, crossRot, star, line, and dash.	Optional	circle triangle rect rectRounded rectRot cross crossRot star line dash

steppedline	If true, the line is shown as a stepped line.	Optional	true
			false
Binding Bar			
labelprop	Name of the adapter parameter, which contains the label value. The field is generated as child of the valueprop field of the RCHART control.	Optional	
backgroundcolorprop	The name of the adapter parameter which provides the backgroundcolor value.	Optional	
borderwidthprop	The name of the adapter parameter which provides the borderwidth value	Optional	
bordercolorprop	The name of the adapter parameter which provides the bordercolor value	Optional	
hoverbackgroundcolorprop	The name of the adapter parameter which provides the hoverbackgroundcolor value.	Optional	
hoverborderwidthprop	The name of the adapter parameter which provides the hoverborderwidth value.	Optional	
hoverbordercolorprop	The name of the adapter parameter which provides the hoverbordercolor value.	Optional	
Binding Line			
labelprop	(already explained above)		
backgroundcolorprop	(already explained above)		
borderwidthprop	(already explained above)		
bordercolorprop	(already explained above)		
borderdashprop	The name of the adapter parameter which provides the borderdash value	Optional	
pointbordercolorprop	The name of the adapter parameter which provides the pointbordercolor value	Optional	
pointbackgroundcolorprop	The name of the adapter parameter which provides the pointbackgroundcolor value	Optional	
pointborderwidthprop	The name of the adapter parameter which provides the pointborderwidth value	Optional	
pointradiusprop	The name of the adapter parameter which provides the pointradius value	Optional	
pointhoverradiusprop	The name of the adapter parameter which provides the pointhoverradius value.	Optional	
pointhitradiusprop	The name of the adapter parameter which provides the pointhitradius value	Optional	

pointhoverbackgroundcolorprop	The name of the adapter parameter which provides the pointhoverbackgroundcolor value	
pointhoverbordercolorprop	The name of the adapter parameter which provides the pointhoverbordercolor value	
pointhoverborderwidthprop	The name of the adapter parameter which provides the pointhoverborderwidth value	Optional
pointstyleprop	The name of the adapter parameter which provides the pointstyle value	Optional
steppedlineprop	The name of the adapter parameter which provides the steppedline value	Optional

RPIECHART

The RPIECHART control supports rendering the following charts:

- pie charts
- doughnut charts

Example

Several examples and corresponding description are provided in the Natural for Ajax demos.

Properties

Basic			
rcharttype	Type of the chart. Valid values: pie, doughnut.	Optional	pie
			doughnut
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.		
data	A semicolon separated list with the data for the arcs. Example: 10;30;100	Optional	
labels	Semicolon separated list. Example: 2015;2016;2017. In a bar chart these are the labels shown for the x-axis. In a horizontal bar chart these are the labels shown for the y-axis.	_ <u> </u>	label1;label2;label3
labelstextid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	_	

	Do not specify a "name" inside the control if specifying a "textid".		
showvalueinchart	Show the values in the chart. Per default the values are shown as tooltip.	Optional	true false
showvaluefontfamily	The font family which is used to show the value.	Optional	
showvaluefontstyle	The font style which is used to show the value.	Optional	
showvaluefontsize	The font size which is used to show the value.	Optional	1
			2
			3
			int-value
showvaluefontcolor	Color of the control. Value must follow format "#rrggbb", e.g. #000000 for black.	Optional	#FF0000
	and the second s		#00FF00
			#0000FF
			#FFFFFF
			#808080
			#000000
showtooltip	If set to false tooltips are disabled. Default is	Optional	true
	true.		false
showpercentage	If set to true the value is shown in percentage. Default is false.	Optional	true
	Default is faise.		false
backgroundcolor	The fill color of the bars or the fill color under	Optional	#ffff00
	the lines or the fill color of the arcs depending on the chart type.		rgb(255, 255, 0)
			hsl(60, 100%, 50%)
borderwidth	Border width in pixels.	Optional	2
			4
			6
bordercolor	Border color.	Optional	#ffff00
			rgb(255, 255, 0)

			hsl(60, 100%, 50%)
hoverbackgroundcolor	Background color when hovered.	Optional	#ffff00
			rgb(255, 255, 0)
			hsl(60, 100%, 50%)
hoverborderwidth	Border width in pixel when hovered.	Optional	2
			4
			6
hoverbordercolor	Border color when hovered.	Optional	#ffff00
			rgb(255, 255, 0)
			hsl(60, 100%, 50%)
rotation	Starting angle to draw arcs from. Default is -0.5	Optional	-0.5
	* Math.PI.		-2
circumference	Sweep to allow arcs to cover. Default is 2 * Math.PI.	Optional	2
	Math.r I.		6
animaterotate	If true, will animate the rotation of the chart.	Optional	true
			false
animatescale	If true, will animate scaling the Doughnut from the centre.	Optional	true
	the centre.		false
animateselection	Set this to an integer value > 0 if you want the selected slice to have a different radius.	Optional	5
	Example: A value of 10 means that the selected		10
	slice has a 10% bigger radius than the unselected slices.		
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence		
	the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		

	You can combine expressions by appending and separating them with a semicolon.	
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.	
styleclasses	CSS style classes separated by a blank.	Optional
onclickmethod	The event which is triggered in the Natural program when for instance a bar of a bar chart is clicked.	Optional
legendclickmethod	Name of the event which is triggered when clicking on a legend.	Optional
Binding		
rcharttypeprop	Name of the adapter parameter that provides as value the type of the chart. Valid values are pie and doughnut.	Optional
dataprop	The name of the adapter parameter which provides the data for the arcs at runtime. The value must be a semicolon separated list. Example: 10;20;30	Optional
labelsprop	Name of the adapter parameter, which contains the label values as semicolon separated list. Example: 2015;2016;2017.	Optional
backgroundcolorprop	The name of the adapter parameter which provides the backgroundcolor value.	Optional
borderwidthprop	The name of the adapter parameter which provides the borderwidth value	Optional
bordercolorprop	The name of the adapter parameter which provides the bordercolor value	Optional
hoverbackgroundcolorprop	The name of the adapter parameter which provides the hoverbackgroundcolor value.	Optional
hoverborderwidthprop	The name of the adapter parameter which provides the hoverborderwidth value.	Optional
hoverbordercolorprop	The name of the adapter parameter which provides the hoverbordercolor value.	Optional
rotationprop	The name of the adapter parameter which provides the rotation value	Optional
circumferenceprop	The name of the adapter parameter which provides the circumference value	Optional
animaterotateprop	The name of the adapter parameter which provides the animaterotate value	Optional

animatescaleprop	The name of the adapter parameter which provides the animatescale value	Optional	
selectedlabelprop	Name of the adapter parameter to which the value of the selected label is set on click.	Optional	
changeindexprop	Name of the adapter parameter providing a value which indicates whether the control should be refreshed with new data on the client or not. A different value than the previous triggers the refresh. It does not need to be a higher value.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	
width	Width of the control.	Optional	100
	There are three possibilities to define the width:		120
	(A) You do not define a width at all. In this case the width of the control will either be a default	I .	140
	width or - in case of container controls - it will		160
	follow the width that is occupied by its content.		180
	(B) Pixel sizing: just input a number value (e.g. "100").		200
	(C) Percentage sizing: input a percantage value		50%
	(e.g. "50%"). Pay attention: percentage sizing will only bring up correct results if the parent element of the control properly defines a width this control can reference. If you specify this		100%
	control to have a width of 50% then the parent element (e.g. an ITR-row) may itself define a width of "100%". If the parent element does not specify a width then the rendering result may		
	not represent what you expect.		
height	Height of the control.	Optional	100
	There are three possibilities to define the height:		150
	(A) You do not define a height at all. As		200
	consequence the control will be rendered with its default height. If the control is a container		250
	control (containing) other controls then the height of the control will follow the height of		300
	its content.		250
	(B) Pixel sizing: just input a number value (e.g. "20").		400

(C) Per	centage sizing: input a percentage value	50%
(e.g. "50	9%"). Pay attention: percentage sizing	
will on	y bring up correct results if the parent	100%
elemen	t of the control properly defines a height	
this con	atrol can reference. If you specify this	
control	to have a height of 50% then the parent	
elemen	t (e.g. an ITR-row) may itself define a	
height	of "100%". If the parent element does not	
specify	a width then the rendering result may	
not rep	resent what you expect.	

11 Responsive Media Controls

■ BMOBILE:VIDEO	190
■ BMOBILE:MEDIAUPLOAD, BMOBILE:MEDIAPREVIEW, BMOBILE:MEDIAPREVIEWBUTTON as	
BMOBILE:MEDIAUPLOADBUTTON	191
BMOBILE:IMAGEFILEUPLOAD, BMOBILE:IMAGEPREVIEW, BMOBILE:IMAGEPREVIEWBUTTO	ON and
BMOBILE:IMAGEUPLOADBUTTON	199

BMOBILE:VIDEO

The BMOBILE: VIDEO control supports the integration of a video, a web cam or a camera into a responsive container.

Example

Several examples and corresponding description are provided in the Natural for Ajax demos.

Properties for BMOBILE:VIDEO

Basic			
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
videourl	URL of the video file	Optional	
videotype	Type of the video format. Default is video/mp4.	Optional	video/mp4 video/ogg video/webm
videotypeprop	Name of the adapter parameter that dynamically defines the video format at runtime. Default value of the video format is video/mp4.	Optional	
videocontrols	Set this property to true if you want the controls for starting, pausing, resumingof the video to be shown.	Optional	true false
autoplay	If set to true the video automatically starts playing when the page is loaded.	Optional	true false
autoplayprop	Name of the adapter parameter that dynamically defines if a video automatically starts playing. Default is FALSE.	Optional	
aspectratio	Defines the proportional relationship between width and height of the control. Example: 4by3	Optional	1by1 16by9 21by9 4by3
playsinline	Some mobile browsers enter fullscreen mode for videos. Set this to TRUE to not enter fullscreen mode. This is not supported in all browsers.	Optional	true false

comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional
Natural		
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.	Optional
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional

BMOBILE:MEDIAUPLOAD, BMOBILE:MEDIAPREVIEW, BMOBILE:MEDIAPRE-VIEWBUTTON and BMOBILE:MEDIAUPLOADBUTTON

These controls implement the upload of a picture or image taken from a BMOBILE: VIDEO control (video, web cam, camera). The picture or image is uploaded as a BLOB via the XCIOBJECT control.

When dragging the BMOBILE: MEDIAUPLOAD control from the palette to your page layout, several controls are arranged as sub-controls under the BMOBILE: MEDIAUPLOAD. You can arrange the controls differently, change the text for panes and buttons, replace the panes by other controls and style them according to your needs. You have to keep the following controls as sub-controls:

- BMOBILE:MEDIAPREVIEWBUTTON
- BMOBILE:MEDIAUPLOADBUTTON
- BMOBILE:MEDIAPREVIEW
- BMOBILE:VIDEO

You also need to add an NJX: OBJECT control to your page. The Adapter Interface and Built-in Events are described below for the following layout definition:

<bmobile:mediaupload valueprop="mediaupload" >

Adapter Interface

```
1 MEDIAUPLOAD
2 CONTENTID (A) DYNAMIC
1 XCIOBJECTS (1:*)
2 CONTENT (B) DYNAMIC
2 CONTENTID (A) DYNAMIC
2 CONTENTTYPE (A) DYNAMIC
```

The MEDIAUPLOAD. CONTENTID field contains the content ID of the uploaded image in the XCIOBJECTS data structure

Built-in Events

For the example definition above, the event mediaupload on Upload is triggered when the upload button is pressed.

Example

Several examples and corresponding description are provided in the Natural for Ajax demos.

Properties for BMOBILE:MEDIAUPLOAD

Basic			
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
mediatype	Default is camera. If you want the picture to be taken from a video file instead of the camera device, set video.	Optional	video camera
Natural		1	
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are		

	bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	

Properties for BMOBILE:MEDIAPREVIEW

Basic			
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
previewstyle	CSS style definition that is directly passed into this control. With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are: border: 1px solid #FF0000 background-color: #808080 You can combine expressions by appending and separating them with a semicolon. Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your	Optional	
	browser and select the "View source" or "View frame's source" function.		
previewstyleclass	es CSS style classes separated by a blank.	Optional	col-auto
			col
			col-*
			col-sm-*
			col-md-*
			col-lg-*
			col-xl-*

			offset-*
			offset-sm-*
			offset-md-*
			offset-lg-*
			offset-xl-*
			mx-auto
			btn-group
			btn-group-vertical
aspectratio		Optional	1by1
	and height of the control. Example: 4by3		16by9
			21by9
			4by3

${\bf Properties\ for\ BMOBILE:} {\bf MEDIAPREVIEWBUTTON}$

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid".	Optional	
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
type	The type of the button like reset or submit.	Optional	button submit file reset
renderaslink	If set to "TRUE" the control is rendered as a link.	Optional	true false

title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		
Appearance		1	ı
styleclasses	CSS style classes separated by a blank.	Optional	btn-default
			btn-primary
			btn-info
			btn-success
			btn-warning
			btn-danger
			btn-sm
			btn-lg
			btn-icon-sm
			btn-icon-lg
			btn-responsive
			btn-outline-primary
			btn-outline-info
			btn-outline-success
			btn-outline-warning
			btn-outline-danger
			close
			mx-auto
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:	1	
	border: 1px solid #FF0000		
	background-color: #808080		

	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		cleared
	(3)"cleared": the control is not visible but it still occupies space.		
straighttext	If the text of the control contains HTML tags then these are	Optional	true
	by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.		false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
Binding			
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	
	,		<u> </u>

Properties for BMOBILE:MEDIAUPLOADBUTTON

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
	Do not specify a "name" inside the control if specifying a "textid".		
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
type	The type of the button like reset or submit.	Optional	
			submit
			file
			reset
renderaslink	If set to "TRUE" the control is rendered as a link.	Optional	
			false
title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		
Appearance			
styleclasses	CSS style classes separated by a blank.	Optional	btn-default
			btn-primary
			btn-info
			btn-success
			btn-warning
			btn-danger
			btn-sm
			btn-lg
			btn-icon-sm

			btn-icon-lg
			btn-responsive
			btn-outline-primary
			btn-outline-info
			btn-outline-success
			btn-outline-warning
			btn-outline-danger
			close
			mx-auto
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		cleared
	(3)"cleared": the control is not visible but it still occupies space.		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		

titlestraighttext	If the text of the control contains HTML tags then these are	Optional	true
	by default interpreted by the browser. Specifiying		
	STRAIGHTTEXT as "true" means that the browser will		false
	directly render the characters without HTML interpretation.		
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
Binding		I.	
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

BMOBILE:IMAGEFILEUPLOAD, BMOBILE:IMAGEPREVIEW, BMOBILE:IMAGE-PREVIEWBUTTON and BMOBILE:IMAGEUPLOADBUTTON

When dragging the BMOBILE: IMAGEFILEUPLOAD control from the palette to your page layout, several controls are arranged as sub-controls under the BMOBILE: IMAGEFILEUPLOAD control. You can arrange the controls differently, change the text, replace the container controls by other containers and style them according to your needs. You must keep the following controls as sub-controls:

- BMOBILE: IMAGEPREVIEWBUTTON
- BMOBILE: IMAGEUPLOADBUTTON
- BMOBILE: IMAGEPREVIEW

You also need to add an NJX: OBJECT control to your page. When pressing the Upload button, an event is triggered in the Natural program.

The Adapter Interface and Built-in Events are described below for the following layout definition:

<bmobile:imagefileupload valueprop="imagefileupload" fileinfoprop="myfileinfo" >

Adapter Interface

```
DEFINE DATA LOCAL

1 IMAGEFILEUPLOAD

2 CONTENTID (A) DYNAMIC

1 MYFILEINFO (A) DYNAMIC

1 XCIOBJECTS (1:*)

2 CONTENT (B) DYNAMIC

2 CONTENTID (A) DYNAMIC

2 CONTENTID (A) DYNAMIC
```

The IMAGEFILEUPLOAD.CONTENTID field contains the content ID of the uploaded image in the XCIOBJECTS data structure. The client side filename is used as content ID. In this example, a fileinformop property is defined. The corresponding IMAGEFILEUPLOAD.MYFILEINFO field will contain information such as the file name and the file size.

The maximum allowed size for upload depends on the configuration of your application server. In a Tomcat installation per default only files less than 2 MB are allowed for upload. You can change this limit in your application server. If you want to upload big files to Natural you also need to increase the Natural configuration parameter Buffer Sizes/Work Area Size correspondingly.

Built-in Events

For the example definition above, the event imagefileupload on Upload is triggered when the upload button is pressed.

Example

Several examples and corresponding description are provided in the Natural for Ajax demos.

Properties for BMOBILE:IMAGEFILEUPLOAD

Basic		
valueprop	Name of the adapter parameter that provides the content of the control.	Obligatory
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional
fileinfoprop	Name of the adapter parameter that contains information of the file like name and size.	Optional
Natural		
njx:natname	If a Natural variable with a name not valid for Application Designer (for instance #FIELD1) shall be bound to the control, a different name (for instance HFIELD1) can be bound instead. If the original name (in this case #FIELD1) is then specified in this attribute, the original name is generated into the parameter data area of the Natural adapter and a mapping between the two names is generated into the PROCESS PAGE statement of the	

	Natural adapter. This mapping must not break a once defined group structure. If for instance a grid control that is bound to a name of GRID1 contains fields that are bound to FIELD1 and FIELD2 respectively, the corresponding njx:natname values may be #GRID1.#FIELD1 and #GRID1.#FIELD2, but not #GRID1.#FIELD1 and #MYGRID1.#FIELD2.		
njx:natstringtype	If the control shall be bound to a Natural system variable of string format with the attribute njx:natsysvar, this attribute indicates the format of the string, A (code page) or U (Unicode). The default is A.	Optional	
njx:natcomment	The value of this attribute is generated as comment line into the parameter data area of the Natural adapter, before the field name. The Map Converter, for instance, uses this attributes to indicate for a generated statusprop variable to which field the statusprop belongs.	Optional	

Properties for BMOBILE:IMAGEPREVIEW

Basic			
previewstyle	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style		
	definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
previewstyleclasses	CSS style classes separated by a blank.	Optional	col-auto
			col
			col-*
			col-sm-*
			col-md-*
			col-lg-*
			col-xl-*
			offset-*

			offset-sm-*
			offset-md-*
			offset-lg-*
			offset-xl-*
			mx-auto
			btn-group
			btn-group-vertical
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	

${\bf Properties\ for\ BMOBILE:} {\bf IMAGEPREVIEWBUTTON}$

Basic			
name	Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
textid	Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a	Optional	
	"textid".		
comment	Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
type	The type of the button like reset or submit.	Optional	button
			submit
			file
			reset
renderaslink	If set to "TRUE" the control is rendered as a link.	Optional	true
			false
title	Text that is shown as tooltip for the control.	Optional	
	Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.		

Appearance			
styleclasses	CSS style classes separated by a blank.	Optional	btn-default
			btn-primary
			btn-info
			btn-success
			btn-warning
			btn-danger
			btn-sm
			btn-lg
			btn-icon-sm
			btn-icon-lg
			btn-responsive
			btn-outline-primary
			btn-outline-info
			btn-outline-success
			btn-outline-warning
			btn-outline-danger
			close
			mx-auto
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		

invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying any space.		disabled cleared
	(2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		
	(3)"cleared": the control is not visible but it still occupies space.		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying	Optional	true
	STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.		false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
titlestraighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		
Binding			
visibleprop	Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	Optional	
nameprop	Name of adapter parameter which dynamically provides the text that is shown inside the control.	Optional	
titleprop	Name of the adapter parameter that dynamically defines the title of the control. The title is displayed as tool tip when ther user moves the mouse onto the control.	Optional	
Miscellaneous			
testtoolid	Use this attribute to assign a fixed control identifier that can be later on used within your test tool in order to do the object identification	Optional	

Properties for BMOBILE:IMAGEUPLOADBUTTON

Text that is displayed inside the control. Please do not specify the name when using the multi language management - but specify a "textid" instead.	Optional	
Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime.	Optional	
Do not specify a "name" inside the control if specifying a "textid".		
Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view.	Optional	
The type of the button like reset or submit.	Optional	button submit file reset
If set to "TRUE" the control is rendered as a link.	Optional	true false
Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	Optional	
CSS style classes separated by a blank.	Optional	btn-default btn-primary btn-info btn-success btn-warning btn-danger
	specify the name when using the multi language management - but specify a "textid" instead. Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid". Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view. The type of the button like reset or submit. If set to "TRUE" the control is rendered as a link. Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.	specify the name when using the multi language management - but specify a "textid" instead. Multi language dependent text that is displayed inside the control. The "textid" is translated into a corresponding string at runtime. Do not specify a "name" inside the control if specifying a "textid". Comment without any effect on rendering and behaviour. The comment is shown in the layout editor's tree view. The type of the button like reset or submit. Optional If set to "TRUE" the control is rendered as a link. Optional Text that is shown as tooltip for the control. Either specify the text "hard" by using this TITLE property - or use the TITLETEXTID in order to define a language dependent literal.

			btn-icon-lg
			btn-responsive
			btn-outline-primary
			btn-outline-info
			btn-outline-success
			btn-outline-warning
			btn-outline-danger
			close
			mx-auto
style	CSS style definition that is directly passed into this control.	Optional	
	With the style you can individually influence the rendering of the control. You can specify any style sheet expressions. Examples are:		
	border: 1px solid #FF0000		
	background-color: #808080		
	You can combine expressions by appending and separating them with a semicolon.		
	Sometimes it is useful to have a look into the generated HTML code in order to know where direct style definitions are applied. Press right mouse-button in your browser and select the "View source" or "View frame's source" function.		
invisiblemode	This property has three possible values:	Optional	invisible
	(1) "invisible": the control is not visible without occupying		disabled
	any space. (2) "disabled": the control is deactivated: it is "grayed" and does not show any roll over effects any more.		cleared
	(3)"cleared": the control is not visible but it still occupies space.		
straighttext	If the text of the control contains HTML tags then these are by default interpreted by the browser. Specifiying STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation.	Optional	true false
	Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true".		

titlestraighttext	
STRAIGHTTEXT as "true" means that the browser will directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true". Binding visibleprop Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	
directly render the characters without HTML interpretation. Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true". Binding visibleprop Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	
Example: if you want to output the source of an HTML text then STRAIGHTTEXT should be set to "true". Binding visibleprop Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	
then STRAIGHTTEXT should be set to "true". Binding visibleprop Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	
Binding visibleprop Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	
visibleprop Name of the adapter parameter that provides the information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	
information if this control is displayed or not. As consequence you can control the visibility of the control dynamically.	
consequence you can control the visibility of the control dynamically.	
dynamically.	
nameprop Name of adapter parameter which dynamically provides Optional	
the text that is shown inside the control.	
titleprop Name of the adapter parameter that dynamically defines Optional	
the title of the control. The title is displayed as tool tip when	
ther user moves the mouse onto the control.	
Miscellaneous	
testtoolid Use this attribute to assign a fixed control identifier that Optional	
can be later on used within your test tool in order to do the	
object identification	

12

Controls for Responsive and Non-Responsive Pages

The following controls and hot keys can be used in responsive as well as in non-responsive scenarios:

AUTOCOMPLETE

OPENSTREETMAP

REPORT2

TIMER

XCIDATADEF - Data Definition

XCICONTEXT

Extended Hot Key Management

Function Key Handling

NJX:OBJECTS

NJX:SESSIONPARAMS

NJX:REQUESTCONTEXT

NJX:TRIGGEREVENT

NJX:XCIOPENPOPUP

NJX:EVENTDATA

13 Styling a Responsive Page

212
216
218
227

Responsive Pages Basics

- Responsive Page Layout
- The styleclasses Property
- The style Property

Responsive Page Layout


Responsive pages adapt the layout to the device. The page renders well on a variety of devices and window or screen sizes without designing different pages for different devices.

Responsive pages are based on the Bootstrap framework 4.6 (refer to https://getbootstrap.com/docs/4.6/).

Responsiveness is achieved via CSS (Cascading Style Sheets) and the Bootstrap grid system. The Bootstrap grid system is made up of:

- Containers
- An unlimited number of rows per container
- A maximum of 12 columns per row

The following shows the basic layout of a responsive page in NJX:



You usually have one bmobile:container control. Under this you place several bmobile:row containers as subnodes. Each row is divided into a maximum of 12 columns. The bmobile:col control spans 1-12 columns. All bmobile:col controls of a bmobile:row should not span more than 12 columns altogether.

In the example above the bmobile:rows each have 6 bmobile:col controls. Each bmobile:col spans 2 columns on every device. The number of columns spanned by a bmobile:col is specified via CSS. The corresponding CSS style class is set as value in the property styleclasses.

Bootstrap supports the setting of device-dependent style classes. The naming convention is:

- *none* (for phones screens less than 576px wide)
- sm (for phones screens equal to or greater than 576px wide)
- md (for tablets screens equal to or greater than 778px wide)
- Ig (for desktops screens equal to or greater than 992px wide)
- xl (for wide desktops screens equal to or greater than 1200px wide)

The class col-6 defines that the control spans 6 columns on an extra small device. Classes for different devices can be combined. Each class scales up, so if you wish to set the same widths for extra small, small (=sm) and medium (=md) devices you only need to specify the extra small class – like col-6.

Based on this you place your controls into rows/cols so that the layout adapts to the different sizes of different devices.

Example:

On a large device like a desktop, you want to arrange several input controls side by side in one row:



But on a small device like a smartphone you want to arrange the input controls underneath each other:



For the example above the following classes have been specified in the NJX layout:

It defines a row with 2 bmobile:col controls. Each control spans 12 columns on extra small and small devices and 6 columns on medium and larger devices. It's sufficient to specify the classes for the extra small (col-12) and medium (col-md-6) devices. When 12 columns are reached the next control is rendered underneath.

The styleclasses Property

Rendering including responsiveness is based on CSS. The responsive controls of NJX are built with Bootstrap which brings a set of style classes for its components.

Many of the style classes are applied automatically to the controls. You don't need to do anything or even know about them.


But especially the Bootstrap framework also supports many style classes which you can additionally apply to use the powerful features of Bootstrap. You can set these classes as values of the styleclasses property in the corresponding control.

- Using Bootstrap Style Classes
- Using Own Style Classes

Using Bootstrap Style Classes


Some of the most popular Bootstrap classes for a control are shown in the Properties view of the Layout Painter. Clicking on the button to the right of the styleclasses property, opens a dialog. You can select from the suggested styleclasses. The text below the selected class explains its usage. Add one, or several classes. Classnames of any classes can be applied when separated by a blank.

The following shows an example from the NaturalAjaxDemos:



You can also add general, control-independent style classes from Bootstrap which are not in the drop-down box.

Below is an example for the Bootstrap .mark style class:



Here you find a complete list of the Bootstrap classes: https://www.w3schools.com/bootstrap4/bootstrap4/bootstrap_ref_all_classes.asp.

The current version of Natural for Ajax is based on Bootstrap 4.6.

Using Own Style Classes


Like with non-responsive pages you can also apply an additional CSS file to a layout page via setting the property addstylesheetfile in the NATPAGE control. Then you can also use any of your own CSS classes from your stylesheet file in the styleclasses property.

The style Property

Settings in the style property overwrite the style classes. The style details of style classes are defined in a .css style sheet file. You can easily change the .css file without changing the layouts. Also, you just define a style class once and re-use it in many layouts. When using the style property, the style is set hard coded in the controls. We recommend using style classes whenever possible. There are some rare situations in which you want to adapt the style just for a few controls in a single layout. In these cases, you use the style property.

Example:

In the example below you use a style="text-align:center" to center text.



Another situation in which you might want to use the style property is in macro controls. A macro control is defined in a central location and just re-used. This allows to change the value of a style property in only one place and re-use the macro control in many layouts.


Stylesheets of an NJX Application

Besides the Bootstrap style classes, NJX itself defines some NJX-specific style classes. Ultimately, the responsive grids are built with the DataTables framework, which also brings a set of style classes.

A responsive NJX page which contains responsive grids automatically includes the following style sheet files:

- A Bootstrap style sheet file, which contains the style classes for all Bootstrap components.
- A DataTables style sheet file, which contains the style classes for grids.

- A style sheet file, which contains NJX-specific style classes.
- Optional: An own additional stylesheet.



The Bootstrap Stylesheet

NJX contains a default Bootstrap CSS file with the name *bootstrap.min.css*. This is automatically applied to each responsive page layout.

The DataTables Stylesheets

NJX uses DataTables (https://datatables.net/) for the responsive grids. It includes 2 alternative CSS files to render the BMOBILE:SIMPLEGRID control:

- 1. dataTables.bootstrap4.css.min: Includes style classes for styling based on Bootstrap 4. It integrates well with the Bootstrap CSS. For instance, the buttons of the grid are styled according to the applied Bootstrap theme.
- 2. jquery.dataTables.css.min: Includes style classes for styling based on the JQuery UI.

Per default NJX uses the dataTables.bootstrap4.min.css. But you can change this default per layout page. Simply set the url of the jquery.dataTables.css in the datatablesstylesheetfile property of the NATPAGE tag.

The style classes are applied automatically to the controls. You don't need to know about these classes or even set them in the styleclasses property. It's all done for you by the NJX framework.

The NJX-Specific Stylesheets

NJX provides style classes to render controls. For non-responsive page layouts, the file <*my-webapp*>/*cis/styles/CIS_DEFAULT.css* is applied per default. For responsive page layouts, NJX applies the file <*mywebapp*>/*cis/styles/responsive/BMOBILE4_Default.css* per default.

Some of the style classes in *BMOBILE4_Default.css* adapt the style classes defined for Bootstrap and/or DataTables slightly. Some of the defined style adds new classes to render NJX controls like the BMOBILE:DATATREE and the BMOBILE:SIDEBAR* controls or adds helper classes, which you can use in the styleclasses property to adapt the rendering correspondingly.

The single style settings are described directly in the file BMOBILE4_Default.css as comments.



Important: DO NOT MODIFY THE *BMOBILE4_Default.css* DIRECTLY! Instead, follow the customization guide in the next section to adapt settings.

Applying your Specific Application Style

In most cases you want to apply your own specific style to your application – with your company or product's colors and shapes. The following describes the steps:

- 1. Set your Bootstrap theme.
- 2. Rebuild your NJX-specific Style Classes with your Bootstrap theme and set the adapted NJX-specific classes.
- 3. Optional: Customize your NJX-specific Style Classes.
- 4. Optional: Set your Datatables theme. Usually this is not required because the Datatables style automatically adapts very well to the Bootstrap theme.
- 5. Optional: Add your own additional style sheet.
 - Set your Bootstrap Theme
 - Rebuild, Customize and Set an NJX-Specific CSS File

Set your DataTables Theme

Set your Bootstrap Theme

NJX uses Bootstrap components to implement the responsive NJX controls. All Bootstrap style classes for the existing Bootstrap components are included in a .css file. Variations of this .css file exist which apply different looks and feels. These variations are called themes. One theme might define a blue button color and another theme might define a grey button color or rounded corners. NJX includes the Cerulean theme from https://bootswatch.com/cerulean/for Bootstrap version 4 as default.

How to Create or Get a Bootstrap Theme

If you want to use a different theme in your NJX applications, you basically have 3 options:

- 1. Download a free theme. Several providers of free themes exist. One example is https://bootswatch.com.
- 2. Buy a theme from corresponding theme providers.
- 3. Create your own theme. To create your own theme, some theme builder tools exist. An example is https://bootstrap.build/

In all 3 cases the result is a .css file containing the corresponding Bootstrap classes. Normally the name for the minified file is *bootstrap.min.css*.




Note: We cannot guarantee that any downloadable samples or output produced by such third-party services or tools will be fully compatible. Before using and downloading, please check the licenses under which the web service, the tool or the output are provided by the authors.

How to Set a Bootstrap Theme in NJX

Per default, NJX uses the Bootstrap theme <*mywebapp*>/HTMLBasedGUI/bootstrap4/css/boostrap.min.css.

If you want to set a different Bootstrap theme in your responsive page layout, do the following:

- In your NaturalONE project, place the bootstrap.min.css into the styles subfolder of your User Interface Component. If you have several User Interface Components, create a "Global User Interface Component" – as described in the NaturalONE documentation - and place it there.
- 2. If you only want to set this theme for a single layout and not the complete application you can use the responsivestylesheetfile property in the NATPAGE to set your Bootstrap theme as shown in the example below:



3. If you want to set your own Bootstrap theme for the whole application, you can create a corresponding NATPAGE template – as described in the documentation *NaturalONE* > *Ajax Developer* > *Getting Started with the Layout Painter* > *Creating Custom Layout Templates* – and set the responsivestylesheetfile property in your template. Alternatively, you can set the attribute defaultresponsivess in the cisconfig.xml file as shown below:

```
<cisconfig ↔
defaultresponsivecss="../myuserinterfacecomponent/styles/mybootstrap.css"</pre>
```

For more information on how to work with *cisconfig.xml* files in NaturalONE, see the documentation *NaturalONE > Ajax Developer > Getting Started with Ajax Developer > Using Ajax Configuration Files*.

4. If you change defaultresponsiveess in the *cisconfig.xml* file, you need to rebuild the User Interface Components in your Natural ONE projects.

NJX Versions and Bootstrap Versions

NJX versions will be upgraded to higher Bootstrap versions from time to time. Please check the release notes if a new Bootstrap version has been applied. In case a new Bootstrap version has been applied, it is strongly recommended to replace your custom Bootstrap themes with the corresponding themes for this version. It is not guaranteed that the NJX with the new Bootstrap version will work with Bootstrap themes of lower Bootstrap versions.

Bootstrap Themes and SASS


Bootstrap supports *Syntactically Awesome Style Sheets* (**SASS**). This allows you to adapt Bootstrap themes to your needs by setting single variables. The big advantage is that you simply need to set the variables and don't need to rewrite or overwrite the CSS classes themselves. A Bootstrap theme usually also consists of a file with the name *_variables.scss*. This file contains a set of variables you can customize and these variables can be used by other style sheets. This allows you to simply rebuild the NJX-specific style classes with the specific settings of your theme, as explained in the next section. Be sure to create or download the *_variables.scss* file for your theme.

Rebuild, Customize and Set an NJX-Specific CSS File


The default style classes in *BMOBILE4_Default.css* match the style of the default Bootstrap theme used in NJX. If you are using a different Bootstrap theme you usually need to create a stylesheet file which matches the style (colors, fonts, etc.) of your custom Bootstrap theme. You don't need to modify any CSS directly because the NJX-specific style classes are based on the Bootstrap SASS variables. You simply need to rebuild the NJX-specific CSS file.

How to Rebuild an NJX-Specific CSS File


In your NaturalONE, open the context menu (right-click) and then select "New/Responsive Style Sheet" as shown below:



Enter a name for your CSS file in the opened wizard and press "Finish":



This will create the following files in the ./styles subfolder of your User Interface Component:



The table below explains the purposes of the three files in the ./styles subfolder:

File name	Purpose
mystylesheet_build.xml	Ant script which generates the NJX-specific CSS file using the <i>mystylesheet_variables.scss</i> and <i>mystylesheet.scss</i> files.
mystylesheet_variables.scss	SASS variable settings in case you would like to customize the NJX-specific CSS (optional).
mystylesheet.scss	The main SASS file which contains all the imports for the generation. You only need to adapt the first import for your specific Bootstrap theme as described below.

The file *mystylesheet.scss* is opened automatically in an Eclipse editor. The first import statement imports the *_variables.scss* file of the default Bootstrap theme of NJX. You need to adapt the path to the *_variables.scss* file of your Bootstrap theme.

Example:

If you copied your theme to the ./styles/mytheme subfolder of your User Interface Component, you would change the line:

```
@import ↔
"C:/myworkspace/.naturalone/apachetomcat/webapps/cisnatural/HTMLBasedGUI/bootstrap4/scss/bootswatch_cerulean/variables";
```

to

```
@import "mytheme/variables";
```

That's all you need to change in the *mystylesheet.scss* files. For a further example, have a look at the *mydarklynjx.css* in the *njxdemos/styles* folder of the NaturalAjaxDemos.

To generate a CSS file from the SASS files, you need a SASS compiler. Currently NJX does not include a SASS compiler. NJX itself uses the SASS compiler https://github.com/sass/dart-sass, which can be downloaded via npm (see https://sass-lang.com/dart-sass). Be sure to use a Bootstrap 4.6

compatible SASS compiler as described here: https://getbootstrap.com/docs/4.6/getting-started/build-tools/#sass.

The *mystylesheet_build.xml* file is a ready-to-use Ant script for generating the CSS file. All you need to set is the path of your SASS compiler as Variable when running the Ant script.

Example:

```
ant -Dsass=c:/mynpm/npm/sass.cmd
```

The Ant script will create the NJX-specific CSS file *mystylesheet.css* for your Bootstrap theme.

How to Customize an NJX-Specific CSS

Besides regenerating the NJX-specific CSS so that it reflects your Bootstrap theme, you can also customize the NJX-specific CSS classes. Instead of modifying the classes directly, the customization is done via SASS variables. The file <code>./cis/styles/responsive/scss/_njxvariables.scss</code> of your NJX installation contains several variables for the NJX-specific CSS.

If you want to change specific settings, do the following:

- 1. Copy the specific variable definition you want to change from the *_njxvariables.scss* file into your *mystylesheet_variables.scss* file.
- 2. Adapt the settings.
- 3. Rebuild the NJX-specific CSS by running the Ant script *mystylesheet_build.xml* as described above.

You'll find two commented-out examples in the *mystylesheet_variables.scss file*:

How to Set an NJX-Specific CSS File

If you want to set your NJX-specific CSS file in your responsive page layout, do the following:

- 1. For a single layout you can use the stylesheetfile property in the NATPAGE.
- 2. If you want to set it for the whole application, you can create a corresponding NATPAGE template as described in the documentation *NaturalONE* > *Ajax Developer* > *Getting Started with the Layout Painter* > *Creating Custom Layout Templates* and set the styleseheetfile property in your template. Alternatively, you can set the attribute defaultbmobiless in the *cisconfig.xml* file as shown below:

```
<cisconfig ↔
defaultmobilecss="../myuserinterfacecomponent/styles/BMOBILE_Mystyle.css"</pre>
```

For more information on how to work with *cisconfig.xml* files in NaturalONE, see the documentation *NaturalONE* > *Ajax Developer* > *Getting Started with Ajax Developer* > *Using Ajax Configuration Files*.

3. If you changed the defaultbmobiless in the *cisconfig.xml* file, then you need to rebuild your User Interface Components in your NaturalONE projects.

NJX Versions and NJX-Specific CSS Versions

Newer NJX versions often bring new style classes for the new supported features. If you created a custom NJX style sheet file as described above, be sure to check the release notes for more information. Upgrading from NJX 9.1.2 and earlier (Bootstrap 3) to NJX 9.1.3 (Bootstrap 4) requires you to upgrade your style sheet file as described above.

Set your DataTables Theme

Per default, NJX uses the DataTables theme <*mywebapp*>/HTMLBasedGUI/datatables/css/dataTables.bootstrap4.min.css. This renders the responsive grids using the Bootstrap style. As an alternative, you can set the file <*mywebapp*>/HTMLBasedGUI/datatables/css/jquery.dataTables.css as DataTables theme. This renders the responsive grids using the jquery style.

How to Create or Get a DataTables Theme

If you want to customize the rendering for either the "Bootstrap" or the "jquery" styling variant, you can create your own DataTables theme. DataTables provide an online theme creator tool to create own themes with your preferred colors and styles. It also provides downloads of customized stylesheets. For more information see https://datatables.net/manual/styling/ and https://datatables.net/manual/styling/ and https://datatables.net/download/.

The result is a .css file containing the corresponding DataTables style classes.




Note: We cannot guarantee that any downloadable samples or output produced by such third-party services or tools will be fully compatible. Before using and downloading, please check the licenses under which the web service, the tool or the output are provided by the authors.

How to Set a DataTables Theme in NJX

If you want to set a different DataTables theme in your responsive page layout do the following:

- 1. In your NaturalONE project, place the corresponding .css file in the styles subfolder of your User Interface Component. If you have several User Interface Components, create a "Global User Interface Component" as described in the NaturalONE documentation and place the .css file there.
- 2. For a single layout, you can use the datatablesstylesheetfile property in the NATPAGE to set your DataTables theme as shown in the example below:



3. If you want to set your own DataTables theme for the whole application, you can create a corresponding NATPAGE template – as described in the documentation NaturalONE > Ajax Developer > Getting Started with the Layout Painter > Creating Custom Layout Templates – and set the datatablesstylesheetfile property in your template. Alternatively, you can set the attribute defaultdatatablescss in the cisconfig.xml file as shown below:

```
<cisconfig ↔
defaultdatatablecss="../myuserinterfacecomponent/styles/mydatatables.css"</pre>
```

For more information on how to work with *cisconfig.xml* files in NaturalONE, see the documentation *NaturalONE > Ajax Developer > Getting Started with Ajax Developer > Using Ajax Configuration Files*.

4. If you changed the defaultdatatablesess in the *cisconfig.xml* file, you need to rebuild your User Interfaces in your NaturalONE projects.

NJX Versions and DataTables Versions

NJX versions will be upgraded to higher DataTables versions from time to time. Please check the release notes if a new DataTable version has been applied. In case a new DataTable version has been applied, it is strongly recommended to replace your custom DataTables themes by corresponding themes for this version. It is not guaranteed that the NJX with the new DataTables version will work with DataTables themes of lower DataTables versions.

Hints

- Do NOT edit Bootstrap or DataTables themes directly. Otherwise, you need to manually apply these changes for each and every version upgrade. If you have for instance your Bootstrap theme, but just want to modify some settings, then use the SASS variables as described above for the customization.
- Only if this is not possible you could add the corresponding rules to an own additional stylesheet file and set this file in the property addstylesheetfile of the NATPAGE control in your layout page. You need to use the !important statement. The example below changes the font size for buttons in the Bootstrap .btn style class:

```
.btn
{
   font-size: 18px !important;
}
```

- Prefer using the styleclasses property over the style property.
- If you see that you are creating many own additional style classes or having lots of additional style settings directly in your layouts, then consider using a different Bootstrap theme instead.
- Prefer using themes over creating own style classes.
- Always place your custom CSS files in the *styles* subfolder of one User Interface Component. Prefer using a "Global User Interface Component" for this.
- Prefer using the cisconfig.xml settings (defaultbmobilecss, defaultresponsiveess and defaultdatatablesess) over using the corresponding NATPAGE properties in all your layouts.